


GemStone/S 64 BitTM **Installation Guide**

for MacOS on i386
(Development only)

Version 3.5.6

May 2021



INTELLECTUAL PROPERTY OWNERSHIP

This documentation is furnished for informational use only and is subject to change without notice. GemTalk Systems LLC assumes no responsibility or liability for any errors or inaccuracies that may appear in this documentation.

Warning: This computer program and its documentation are protected by copyright law and international treaties. Any unauthorized copying or distribution of this program, its documentation, or any portion of it, may result in severe civil and criminal penalties, and will be prosecuted under the maximum extent possible under the law.

The software installed in accordance with this documentation is copyrighted and licensed by GemTalk Systems under separate license agreement. This software may only be used pursuant to the terms and conditions of such license agreement. Any other use may be a violation of law.

Use, duplication, or disclosure by the Government is subject to restrictions set forth in the Commercial Software - Restricted Rights clause at 52.227-19 of the Federal Acquisitions Regulations (48 CFR 52.227-19) except that the government agency shall not have the right to disclose this software to support service contractors or their subcontractors without the prior written consent of GemTalk Systems.

This software is provided by GemTalk Systems LLC and contributors "as is" and any expressed or implied warranties, including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose are disclaimed. In no event shall GemTalk Systems LLC or any contributors be liable for any direct, indirect, incidental, special, exemplary, or consequential damages (including, but not limited to, procurement of substitute goods or services; loss of use, data, or profits; or business interruption) however caused and on any theory of liability, whether in contract, strict liability, or tort (including negligence or otherwise) arising in any way out of the use of this software, even if advised of the possibility of such damage.

COPYRIGHTS

This software product, its documentation, and its user interface © 1986-2021 GemTalk Systems LLC. All rights reserved by GemTalk Systems.

PATENTS

GemStone software is or has been covered by U.S. Patent Number 6,256,637 "Transactional virtual machine architecture" (1998-2018), Patent Number 6,360,219 "Object queues with concurrent updating" (1998-2018), Patent Number 6,567,905 "Generational garbage collector with persistent object cache" (2001-2021), and Patent Number 6,681,226 "Selective pessimistic locking for a concurrently updateable database" (2001-2021).

TRADEMARKS

GemTalk, **GemStone**, **GemBuilder**, **GemConnect**, and the GemTalk logo are trademarks of GemTalk Systems LLC, or of VMware, Inc., previously of GemStone Systems, Inc., in the United States and other countries.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Solaris, **Java**, and **Oracle** are trademarks or registered trademarks of Oracle and/or its affiliates. **SPARC** is a registered trademark of SPARC International, Inc.

Intel and **Pentium** are registered trademarks of Intel Corporation in the United States and other countries.

Microsoft, **Windows**, and **Windows Server** are registered trademarks of Microsoft Corporation in the United States and other countries.

Linux is a registered trademark of Linus Torvalds and others.

Red Hat and all Red Hat-based trademarks and logos are trademarks or registered trademarks of Red Hat, Inc. in the United States and other countries.

Ubuntu is a registered trademark of Canonical Ltd., Inc., in the U.S. and other countries.

SUSE is a registered trademark of Novell, Inc. in the United States and other countries.

AIX, **POWER6**, **POWER7**, and **POWER8** and **VisualAge** are trademarks or registered trademarks of International Business Machines Corporation.

Apple, **Mac**, **MacOS**, and **Macintosh** are trademarks of Apple Inc., in the United States and other countries.

CINCOM, **Cincom Smalltalk**, and **VisualWorks** are trademarks or registered trademarks of Cincom Systems, Inc.

Other company or product names mentioned herein may be trademarks or registered trademarks of their respective owners. Trademark specifications are subject to change without notice. GemTalk Systems cannot attest to the accuracy of all trademark information. Use of a term in this documentation should not be regarded as affecting the validity of any trademark or service mark.

GemTalk Systems LLC
15220 NW Greenbrier Parkway
Suite 240
Beaverton, OR 97006



Preface

About This Documentation

This document explains how to install GemStone/S 64 Bit version 3.5.6 on a workstation running Mac OS X on i386, and how to upgrade from previous GemStone/S 64 Bit versions.

Terminology Conventions

The term “GemStone” is used to refer to the server products GemStone/S 64 Bit and GemStone/S, and the GemStone family of products; the GemStone Smalltalk programming language; and may also be used to refer to the company.

Technical Support

Support Website

gemtalksystems.com

GemTalk’s website provides a variety of resources to help you use GemTalk products:

- ▶ **Documentation** for the current and for previous released versions of all GemTalk products, in PDF and HTML.
- ▶ **Product download** for the current and selected recent versions of GemTalk software.
- ▶ **Bugnotes**, identifying performance issues or error conditions that you may encounter when using a GemTalk product.
- ▶ **Supplemental Documentation** and **TechTips**, providing information and instructions that are not in the regular documentation.
- ▶ **Compatibility matrices**, listing supported platforms for GemTalk product versions.

We recommend checking this site on a regular basis for the latest updates.

Help Requests

GemTalk Technical Support is limited to customers with current support contracts. Requests for technical assistance may be submitted online (including by email), or by telephone. We recommend you use telephone contact only for urgent requests that require immediate evaluation, such as a production system down. The support website is the preferred way to contact Technical Support.

Website: techsupport.gemtalksystems.com

Email: techsupport@gemtalksystems.com

Telephone: (800) 243-4772 or (503) 766-4702

Please include the following, in addition to a description of the issue:

- ▶ The versions of GemStone/S 64 Bit and of all related GemTalk products, and of any other related products, such as client Smalltalk products, and the operating system and version you are using.
- ▶ Exact error message received, if any, including log files and statmonitor data if appropriate.

Technical Support is available from 8am to 5pm Pacific Time, Monday through Friday, excluding GemTalk holidays.

24x7 Emergency Technical Support

GemTalk offers, at an additional charge, 24x7 emergency technical support. This support entitles customers to contact us 24 hours a day, 7 days a week, 365 days a year, for issues impacting a production system. For more details, contact GemTalk Support Renewals.

Training and Consulting

GemTalk Professional Services provide consulting to help you succeed with GemStone products. Training for GemStone/S is available at your location, and training courses are offered periodically at our offices in Beaverton, Oregon. Contact GemTalk Professional Services for more details or to obtain consulting services.



Table of Contents

Chapter 1. Installing GemStone/S 64 Bit Version 3.5.6

Review the Installation Procedure	7
Check the System Requirements	8
Configure the Operating System	9
Install the GemStone Server.	11
Set the Environment	12
Set the GemStone Key File.	12
Verify TCP/IP	13
Define the NetLDI Service.	13
Run the Installation Script.	14
Complete GemStone Configuration	16
Change Passwords for Administrative Accounts.	16
Add GemStone User Accounts	17
Users must set environment.	17
Install the default TimeZone	17
Further Configuration and Administration	17

Chapter 2. Upgrading from GemStone/S 64 Bit 3.3.x or later

Keyfiles	19
Upgrade Procedure	20
Prior to Upgrade in existing application.	20
Prepare for Upgrade	20
Perform the Upgrade.	22
GsDevKit Upgrade.	23
Post-upgrade Application Code Modifications	23
Make Backup	23
Configure GCI clients and GBS.	23

Chapter 3. Upgrading from 3.2x

Keyfiles	25
Upgrade Procedure	26
Prior to Upgrade in existing application	26
Prepare for Upgrade	27
Perform the Upgrade	28
GsDevKit Upgrade	29
Post-upgrade Application Code Modifications	29
Make Backup	32
Configure GCI clients and GBS	32

Chapter 4. Upgrading GLASS/GsDevKit Applications

Upgrade Procedure	33
1. Ensure that GemStone 3.5.6 is installed and your repository upgraded	34
2. If necessary, customize the upgrade instructions	34
3. Perform the Upgrade.	35
4. Load your Application Code	36
5. Complete the Upgrade Process	36

Chapter 5. Configuring GBS for GemStone/S 64 Bit

Installing GemStone/S 64 Bit Version 3.5.6

This chapter describes the procedure for installing GemStone/S 64 Bit™ version 3.5.6. We recommend that you set up GemStone initially on a single machine, to ensure that all the pieces work together. At the end of this chapter, we suggest refinements you might want to make. Further setup to run a distributed system are described in the *System Administration Guide*. You will need to adjust the installation process to meet your specific needs.

If you are upgrading to this release from a previous version of GemStone/S 64 Bit, follow the instructions in the appropriate later chapter of this Installation Guide. These upgrade instructions will provide details on steps that need to be taken before and after the installation as described in this chapter.

GemStone/S 64 Bit on MacOS is supported for development use only, not for use in production.

Review the Installation Procedure

The following list summarizes the steps to install GemStone/S 64 Bit.

- ▶ Check the System Requirements. 8
- ▶ Install the GemStone Server 11
- ▶ Set the Environment 12
- ▶ Set the GemStone Key File 12
- ▶ Verify TCP/IP 13
- ▶ Define the NetLDI Service 13
- ▶ Run the Installation Script 14
- ▶ Change Passwords for Administrative Accounts 16
- ▶ Add GemStone User Accounts 17
- ▶ Install the default TimeZone 17

Check the System Requirements

Before you install GemStone/S 64 Bit, ensure that the following system requirements are satisfied. Systems meeting these requirements are suitable for installing GemStone/S 64 Bit and beginning development, but additional system resources may be necessary to support large applications.

Platform

- ▶ Intel Core 2 Duo or later

RAM and Swap space

- ▶ While small installations can run on systems with only a few GB of physical RAM, increasing RAM is important for GemStone performance.
- ▶ Adequate free disk space on the machine's boot partition beyond other system needs.

Disk space

- ▶ Space for the installed distribution files—you need approximately 450 MB for GemStone/S 64 Bit, and additional space for other products.
- ▶ Additional disk space as required for your repository.

The repository files should be located on a disk drive that does not contain swap space. Use of multiple disk drives is advisable for servers.

Operating system

- ▶ MacOS 11.1 (Big Sur) with Darwin 20.2.0 kernel
- ▶ MacOS 10.15.6 (Catalina) with Darwin 19.6.0 kernel

Debugger

- ▶ lldb 12.3.0

lldb is installed as part of the Xcode command line tools package.

A debugger is not required for GemStone execution, but is useful for generating GemStone stack traces. You may need to be logged in as root, or as a user with administrative privileges, in order to use a debugger with GemStone processes.

C/C++ Compiler

- ▶ Big Sur: Apple clang version 12.0.0 (clang-1200.0.32.28)
- ▶ Catalina: Apple clang version 11.0.3 (clang-1103.0.33.17)

GemStone requires a C/C++ compiler only if you are developing C or C++ code for user actions or for a C or C++ application. This compiler is required only for development work, not for execution.

X Windows

An X Windows server allows you to use GemStone's graphical VSD application on Mac. Alternatively, GemStone statistical data may be viewed on Windows, by transferring the data files, or by mounting the file system on Windows. X Windows is not required for GemStone execution.

Configure the Operating System

The kernel must be configured to support shared memory and semaphores. See your operating system documentation for further information. These requirements apply both to server nodes and to client nodes.

1. Kernel parameters

In earlier releases of MacOS, to specify shared memory and other kernel parameters, you could define the file `/etc/sysctl.conf` (if it did not exist), or edit the settings in this file, to modify kernel parameters. With "Big Sur", the requirements have changed.

In "Big Sur", you must create a plist file with the name `com.gemtalksystems.shared-memory.plist`, and put this file in `/Library/LaunchDaemons/`.

After defining either of these files, or making changes to the settings, you will need to reboot so the changes take effect.

Shared Memory

The maximum shared memory segment should be set to a value larger than your desired Shared Page Cache size, and not more than 75% of your real memory size. In addition, for most system you will need to increase the system-wide limit on shared memory segments.

Note that `kern.sysv.shmmax` is configured in bytes, but `kern.sysv.shmall` is configured in pages with a base page size of 4096.

For example, if you have 8192 MB of real memory:

$$\begin{aligned} 8192 \text{ MB} * .75 &= 6144 \text{ MB} \\ 6144 \text{ MB} * 2^{20} &= 6442450944 \text{ bytes} \end{aligned}$$

To set shared memory, you would include the following text in the `/etc/sysctl.conf` file, creating this file if it does not exist. The setting of the shared memory size is read from this file during the boot process.

```
# Shared Memory setting for GemStone
kern.sysv.shmmax=6442450944
kern.sysv.shmall=1572864
```

Number of Processes

The default limits on the number of processes are adequate for up to about 250 GemStone users, for configurations establishing security via captive account. To allow more processes for the GemStone administrative userid, increase the settings for `kern.maxprocperuid` and `kern.maxproc` in `/etc/sysctl.conf`.

Setting kernel parameters

The following example contents of `com.gemtalksystems.shared-memory.plist` would apply to a system with 8MB of RAM, as described above.

You may download this file, and update with your required settings, from: <https://docs.gemtalksystems.com/current/com.gemtalksystems.shared-memory.plist>

```
<?xml version="1.0" encoding="UTF-8"?>
<!DOCTYPE plist PUBLIC "-//Apple//DTD PLIST 1.0//EN"
"http://www.apple.com/DTDs/PropertyList-1.0.dtd">
<plist version="1.0">
<dict>
  <key>Label</key>
  <string>shmsetup</string>
  <key>UserName</key>
  <string>root</string>
  <key>GroupName</key>
  <string>wheel</string>
  <key>ProgramArguments</key>
  <array>
    <string>/usr/sbin/sysctl</string>
    <string>kern.sysv.shmmax=6442450944</string>
    <string>kern.sysv.shmall=1572864</string>
  </array>
  <key>KeepAlive</key>
  <false/>
  <key>RunAtLoad</key>
  <true/>
</dict>
</plist>
```

2. PAM

If you are using UNIX authentication for GemStone logins, or if you run NetDLI as root with `setuid` (i.e. not in guest mode), you must have PAM (Pluggable Authentication Module) configured on the server. You may include a specific GemStone authorization service name, or allow the default “other” authentication definitions to be used.

PAM authentication definitions are files under the directory `/etc/pam.conf/`.

The specific GemStone service file names are `gemstone.gem` for user authentication, and `gemstone.netldi` for a NetLDI running with authentication.

The libraries that are specified in the stack depend on how you are configuring PAM to perform the authentication. The examples below are for PAM configured to invoke LDAP for authentication.

For example, to allow GemStone UNIX authentication, which uses PAM, to authenticate via LDAP, create a file named `/etc/pamd.conf/gemstone.gem` with the following contents:

```
auth required pam_opendirectory.so
```

Note that this is for GemStone UNIX authentication, not for GemStone LDAP authentication. When you configure GemStone authentication as LDAP, it authenticated directly with LDAP, not via PAM.

For NetLDI authentication, again using LDAP, create a file named `/etc/pam.d.conf/gemstone.netldi` with the following contents:

```
auth                required                pam_opendirectory.so
```

You can allow the “other” authentication stack to be used for GemStone authentication by editing the file `/etc/pam.d.conf/other` so it includes the following:

```
auth                required                pam_opendirectory.so
```

Consult your System Administrators for more information on how authentication is handled on your system.

3. System clock

The system clock must be set to the correct time. When GemStone opens the repository at startup, it compares the current system time with the recorded checkpoint times as part of a consistency check. A system time earlier than the time at which the last checkpoint was written may be taken as an indication of corrupted data and prevent GemStone from starting. The time comparisons use GMT.

4. TCP keepalive option

GemStone processes ordinarily use the `TCP keepalive` option to determine how long they will wait after communications activity ceases unexpectedly. This setting can be useful for reaping stale RPC Gems, but the operating system default may not be appropriate for this purpose. For further information, refer to your operating system documentation.

Install the GemStone Server

Installing GemStone can be done as a regular user, but in order to set up shared security, some portions of the installation should be done when logged in as the root user. Other steps of the installation are done as the unix user who will be the GemStone administrative account.

In addition to the installation directory, these are the portions of the system that are affected by the installation of GemStone:

```
/dev/rdisk*
```

Optional raw partitions for repository extents and transaction logs.

```
/etc/services
```

Internet services database, for NetLDI name lookup.

```
/opt/gemstone
```

Default location for server lock files, host name id file, and log files for GemStone network servers (NetLDIs). See the *System Administration Guide* for details.

1. Log in as the GemStone administrator to the machine on which you are installing GemStone. This part of the installation should **not** be done as root, to ensure all the files are not owned by root.
2. Determine that adequate swap space is available.:
3. Select the drive on which you will install the GemStone software, and the installation directory on this drive, *InstallDir*. Make this directory the current working directory.

We recommend that you avoid choosing either an NFS-mounted partition or one containing UNIX swap space for the initial installation. Mounted partitions can result in executables running on the wrong machine and in file permission problems. Existence of swap space on the same drive can dramatically slow GemStone disk accesses.

4. GemStone/S 64 Bit is provided as a .dmg file with a name similar to `GemStone64Bit3.5.6-i386.Darwin.dmg`.
5. Double click on this file to open it, and drag the installation tree to *InstallDir*.
6. The *InstallDir* now contains a GemStone directory with a name similar to `GemStone64Bit3.5.6-i386.Darwin`.

In addition to subdirectories, this directory also contains two text files: `PACKING`, which lists all of the GemStone files, and `version.txt`, which identifies this particular product and release of GemStone.

The GemStone server is now installed.

Set the Environment

Perform the following steps to properly configure the operating environment.

1. Set the environment variable GEMSTONE.
 - a. If more than one installation of any GemStone/S product resides on this machine, check for existing GemStone environment variables:

```
> env | grep GEM
```

All GemStone environment variables are displayed.
 - b. If any environment variables exist and are not appropriate for the new installation, you must specifically unset each one. For example:

```
> unset GEMSTONE GEMSTONE_SYS_CONF
```
 - c. Set the environment variable GEMSTONE to the *full pathname* (starting with a slash) of your new GemStone installation directory. For example:

```
> export GEMSTONE=InstallDir/GemStone64Bit3.5.6-i386.Darwin
```

Set the GemStone Key File

To run GemStone, you must have a key file for the correct version of GemStone/S 64 Bit and for the appropriate platform. The keyfile must be located where GemStone can find it on startup:

- ▶ A file specified by the KEYFILE configuration parameter in the configuration file used by the stone. This is not set by default, but may be defined to read a keyfile with any name in any location.
- ▶ `$GEMSTONE/sys/gemstone.key`
- ▶ `$GEMSTONE/sys/community.starter.key`

Licensed Customer key file

You may use a keyfile from any v3.5.x version with v3.5.6; keyfiles from 3.4.x and earlier are not valid with v3.5.6. If you are upgrading from v3.4.x or earlier, or you have questions

about your keyfile or license limits, email keyfiles@gemtalksystems.com, or contact GemTalk Technical Support.

Community key file

The GemStone distribution includes a community key file, `community.starter.key`, with product and system limits per the Community and Web Edition License. See <https://gemtalksystems.com/licensing> for details on the license terms.

If you do not install a custom keyfile, this starter keyfile will be used instead.

Installing a keyfile

To specify the location and name of the keyfile using the `KEYFILE` configuration parameter, edit the configuration file that will be used by the v3.5.6 stone to include the location and name of the keyfile.

You may also put the keyfile in the default location, `$GEMSTONE/sys/gemstone.key`. This requires modifying the write permissions of the `$GEMSTONE/sys` directory; ensure you change this back to not writable, after this update.

Verify TCP/IP

To run GemStone, TCP/IP must be functioning, even if your machine is not connected to a network.

Verify that TCP/IP networking software is functioning (1 is the number 1):

```
> /sbin/ping -c 1 hostname
```

where *hostname* is the name of your machine. If **ping** responds with statistics, TCP/IP is functioning.

Define the NetLDI Service

The NetLDI service, by default `gs64ldi`, can be defined in your system services database to return the NetLDI listening port. A NetLDI is required for some local and all remote sessions to log into GemStone, and it can be resolved by name or directly by port number. If you are defining NetLDI services by name, the same NetLDI service name and port number must be defined on the remote machines as on the Stone's node.

The following steps can be skipped if you will be using the NetLDI port rather than name. Using the port number requires that this same port be specified when the NetLDI is started up, and when sessions login. The details are described in the *System Administration Guide*.

If you are upgrading from a previous version, you may need to keep the NetLDI for that version running. In this case, select a distinct name and/or port for the NetLDI for GemStone/S 64 Bit 3.5.6.

1. Determine whether the `gs64ldi` service is already defined. How to do this will depend on how your system is set up. The GemStone distribution includes an executable that will allow you to do this:

```
unix> $GEMSTONE/install/getservbyname gs64ldi  
s_name=gs64ldi s_port = 50377 s_proto = tcp
```

If `gs64ldi` is defined, skip the rest of this procedure and continue with the installation at "Run the Installation Script" on page 14.

If it is not defined, continue performing this procedure.

2. Add an entry similar to the following to the system services database:

```
gs64ldi 50377/tcp #GemStone/S 64 Bit 3.5.6
```

Choose a port number that is not being used by another service. The port number should be in the range $49152 \leq \text{port} \leq 65535$, to conform to IANA standards (<http://www.iana.org/assignments/port-numbers>).

3. If several machines will be running GemStone, have the UNIX system administrator update the system services database for each machine. This includes Windows client machines as well as UNIX nodes. Note that the port number must be the same for every machine.

Run the Installation Script

The installation script verifies your environment, creates lock file directories, sets up the extent files, and can be used to configure certain types of security for multi-user systems. It is not required to run the installation script; however, if you are new to GemStone, or installing GemStone on a new server, running the install script is recommended.

1. Log in as root.

You can run the installation script as a non-root user, however, some options are not available as a non-root user. To ensure that the installation is successful, you must install as root. See the *System Administration Guide* for details on setting up GemStone server file security.

2. Invoke the installation script from the `install` subdirectory:

```
unix> cd $GEMSTONE/install
unix> ./installgs
```

`installgs` is an interactive script that analyzes your system configuration and makes suggestions to guide you through installing GemStone on your machine. You can run the script multiple times; it will skip completed tasks.

NOTE

You can usually terminate execution of the installation script with Ctrl-C without risk to your files. When it is not safe to do so, the message `Please do not interrupt` appears on the screen.

During installation, you are asked several questions. The entire installation dialog is not reproduced here, but the main points are addressed. Some questions may not be asked, depending on answers to previous questions.

Whenever you are asked to answer “yes” or “no,” answer with `y` or `n`. When the script offers a default answer in square brackets (such as “[`y`]”), press Enter to accept the default.

Set up directories for server lock files and NetLDI logs?

The default location for server lock files and NetLDI log files is `/opt/gemstone`, although `/usr/gemstone` may be used in legacy installations. A different location can be specified using the environment variable

GEMSTONE_GLOBAL_DIR; however, all Gemstone processes that will interact on this machine must have this environment variable set to the same directory.

If the directory does not exist, the installation script offers to create `/opt/gemstone` and the subdirectories `locks` and `log`, and to set access (770) to these directories.

If you answer no to creating the directories, you must create them (or provide a symbolic link) before starting the server.

Set the owner and group for all the files in the distribution?

If you answer **yes**, the script will prompt you for the owner and group you want to use. Refer to Chapter 1 of the *System Administration Guide* for more information about setting owner and group permissions.

If you answer **no**, the permissions will remain the same as when the files were extracted from the distribution media.

Protect the repository file?

The default gives only the owner read and write access (600) through ordinary UNIX commands. Other users can read and write the repository through a GemStone session. If you choose not to protect the repository, the `setuid` bit is cleared from all executables, which causes them to run under ownership of the user who invokes them.

Default: Set the repository permission to 600, and leave the `setuid` bit applied.

Allow NetLDI to Run as Root?

The NetLDI is a network server that permits remote processes to interact with the repository. There are two ways to set up a NetLDI so that it can provide services to all GemStone users: it can run as root, or it can run in guest mode with a captive account.

- ▶ To run NetLDIs as root, accept the default “yes” response. Ownership of the NetLDI executable is changed to root, and the `setuid` bit is set. Any GemStone user will be able to start a NetLDI process that is accessible to all GemStone users because it will always run as root. For certain services, users will need to authenticate themselves by supplying a password.
- ▶ To run NetLDIs in guest mode with a captive account, answer “no” to the prompt, because those modes are not permitted if the NetLDI runs as root. “Guest mode” means that GemStone users do not have to supply a UNIX password to use NetLDI services. The “captive account” is an account that owns all processes the NetLDI starts; typically, it is the GemStone administrative account that owns the files. You must start the NetLDI while logged in as that account.

Default: Change ownership of the `netldi` executable to root, and set its `setuid` bit.

Set up an Extent?

GemStone is distributed with a read-only copy of the initial repository in `$(GEMSTONE)/bin/extent0.dbf`. Before you can start GemStone, this file must

be copied to a suitable location and made writable. The script offers to copy the file to its default location of `$GEMSTONE/data`.

If you are a new GemStone user, we recommend that you answer `y`. If you are an existing GemStone user, you might prefer to answer `n`, then copy the extent to a different location yourself. (If you choose a location other than the default, you must edit your configuration file before starting GemStone. For information, see the *System Administration Guide*.)

Default: Place a writable copy of `extent0.dbf` in `$GEMSTONE/data`.

Start a NetLDI?

You can start a NetLDI that runs as root by answering yes to this prompt and the confirmation that follows.

However, if you want to start the NetLDI in guest mode with a captive account, you must do that after completing the installation. For more information about guest mode with captive account, see Chapter 3 of the *System Administration Guide*.

Default: Do not start a NetLDI at this time.

Start an Object Server?

As root, you cannot start an object server (Stone), but the script offers to start one as another user.

Default: Do not start an object server at this time.

3. Log out as root

After running `installgs`, log out as user root.

Further work is done as the GemStone administrative user.

Complete GemStone Configuration

The following should be done by an administrative user, not as root.

Change Passwords for Administrative Accounts

GemStone comes with a number of built-in System user accounts, which are needed to perform administrative operations (such as adding application user accounts).

- ▶ The **DataCurator** account is used to perform system administration tasks.
- ▶ The **SystemUser** account ordinarily is used only for performing GemStone system upgrades.
- ▶ The **GcUser** account is used by the garbage collection task, which runs automatically as a separate login.

The initial password for these administrative accounts is `swordfish`.

Access to each of these accounts should be restricted; you should always change the passwords for these accounts, to provide basic security for your application.

The chapter entitled “User Accounts and Security” in the *System Administration Guide* tells you how to change the passwords.

Add GemStone User Accounts

For each of the users in your system, you should establish GemStone accounts, which involves creating an individual UserProfile in GemStone.

The chapter entitled “User Accounts and Security” in the *System Administration Guide* provides information on how create accounts for GemStone users, and the options for authentication. This task can be done by executing Smalltalk code, or using GemBuilder for Smalltalk tools. See the *GemBuilder for Smalltalk Users’s Guide* for information on the GUI tools in GemBuilder.

Users must set environment

After GemStone/S 64 Bit 3.5.6 has been installed, you should notify each person who will be using GemStone about the installation, and explain how to setup their environment.

Each user must:

- ▶ Set the environment variable `GEMSTONE` to the *full pathname* (starting with a slash) of the GemStone/S 64 Bit 3.5.6 directory.
- ▶ update their path to include the `$GEMSTONE/bin` directory.
- ▶ Optionally, update the man path (`MANPATH` variable) to include the `$GEMSTONE/doc` directory. GemStone provides man pages for utility functions.

These last two steps can be done using scripts that are part of the GemStone distribution. The directory `$GEMSTONE/bin` contains the files `gemsetup.sh` and `gemsetup.csh`, which define the GemStone environment for users by modifying the `PATH` and `MANPATH` variables to include `$GEMSTONE/bin` and `$GEMSTONE/doc`, respectively.

For example:

```
unix> export GEMSTONE=installdir
unix> export PATH=$GEMSTONE/bin:$PATH
unix> export MANPATH=$MANPATH:$GEMSTONE/doc
```

If the user will use GemStone frequently, consider adding these steps to the login shell initialization file.

Install the default TimeZone

GemStone/S 64 Bit is shipped with a default time zone of US Pacific. If you are in another Time Zone, edit the file `installtimezone.txt` in the GemStone upgrade directory, then file it in as SystemUser.

Further Configuration and Administration

This chapter has guided you through installation of GemStone/S 64 Bit 3.5.6, with the objective of getting a simple, default configuration up and running.

The next chapters explain the process of upgrading a previous version of GemStone/S 64 Bit to version 3.5.6; and Chapter 5 provides information on GemBuilder for Smalltalk.

For more information and details on customizing your GemStone object server, Gem client processes, and setting up distributed configurations, see the *System Administration Guide*.

Upgrading from GemStone/S 64 Bit 3.3.x or later

This chapter describes how to upgrade an existing GemStone/S 64 Bit 3.3.x, 3.4.x, or 3.5.x installation to GemStone/S 64 Bit version 3.5.6.

For upgrading from GemStone/S 64 Bit versions 3.2.x, which require extra steps such as recompilation, see Chapter 3, starting on page 25.

To upgrade from GemStone/S 64 Bit version 3.1.x and earlier, you must first upgrade to a 3.3.x or 3.4.x version, and then upgrade to v3.5.6.

If you are using GemBuilder for Smalltalk (GBS), you also need to upgrade the client libraries that are used by GBS. You may also need to upgrade your version of GBS; versions of GBS earlier than 8.4 or 5.4.5 are not supported with v3.5.6. See Chapter 5 for details.

Keyfiles

You may use a keyfile from any v3.5.x version with v3.5.6. Keyfiles from 3.4.x and earlier are not valid with v3.5.6.

To acquire a keyfile for version 3.5.6, email keyfiles@gemtalksystems.com, or contact GemStone Technical Support, preferably providing your existing keyfile.

Keyfiles also manage access to GemConnect and GemBuilder for Java, and the recently introduced X509-Secured GemStone feature. If you are using these add-on products, you must use a keyfile with the appropriate permissions.

Upgrade Procedure

The following list summarizes the steps necessary to perform the upgrade to GemStone/S 64 Bit v3.5.6.

- ▶ Prior to Upgrade in existing application. 20
- ▶ Prepare for Upgrade 20
- ▶ Perform the Upgrade 22
- ▶ Post-upgrade Application Code Modifications. 23
- ▶ Make Backup 23
- ▶ Configure GCI clients and GBS. 23

NOTE

The following instructions use the version number 3.4.5 to refer to the version you are upgrading from, and 3.5.6 indicate the target version you are upgrading to.

Prior to Upgrade in existing application

1. Check for use of deprecated methods

Verify that your application does not invoke any methods that were deprecated in previous releases, by enabling error or logging on deprecation in your existing repository. Deprecated methods are subject to removal in major releases; finding them before upgrading allows the deprecation messages to provide replacement instructions.

For details on finding deprecated methods, refer to the *Programming Guide for GemStone/S 64 Bit*.

2. File out modifications to GemStone classes

File out any modifications or additions you made to GemStone/S 64 Bit kernel class methods. For more information about fileout, see the *GemStone/S 64 Bit Topaz Programming Environment*.

You will need to carefully compare these changes with GemStone/S 64 Bit 3.5.6 kernel methods, and refer to the *Release Notes* for version 3.5.6 to determine whether your changes are still necessary or appropriate.

CAUTION

Any changes that you have made to the GemStone/S 64 Bit kernel classes will be lost during upgrade; you MUST file these out in order to preserve the changes in version 3.5.6.

Prepare for Upgrade

1. Install and configure GemStone/S 64 Bit 3.5.6

Install GemStone/S 64 Bit 3.5.6 to a new installation directory, separate from the installation directory for version 3.4.5, as described in Chapter 1, starting on page 7.

Configure GemStone/S 64 Bit 3.5.6 the way you expect to use it — that is, with the appropriate extent locations and sizes.

If you copy the configuration files from your previous version to the version 3.5.6, be sure to review any changes in configuration parameters to determine if changes are needed.

You should ensure that adequate space is available for extents, transaction logs, and a backup during the upgrade. You must provide space for the extents and transaction logs for both repositories, the old and the new.

2. Reset SystemUser password

Log in to the version 3.4.5 system as a user with OtherPassword privilege, such as DataCurator, and reset the SystemUser password to 'swordfish':

```
topaz 1> run
(AllUsers userWithId: #SystemUser) password: 'swordfish' .
System commitTransaction.
%
```

The upgrade script logs in with the SystemUser account and the default password, and resets the password for DataCurator and GcUser.

3. Stop user activity

Log in to the version 3.4.5 system as a user with SessionAccess and SystemControl privileges, such as DataCurator, and halt all user activity on the repository.

```
topaz 1> run
System stopUserSessions.
%
```

4. Shut down the repository

You may now shut down the Stone. At the UNIX command line:

```
unix> stopstone stone345
```

where *stone345* is the name of the version 3.4.5 stone on this machine. The repository must be cleanly shut down to avoid needing recovery when it is restarted with the new version's executables.

5. Set up the version 3.5.6 environment.

Set the environment variables required for the upgrade. For example:

```
export GEMSTONE=InstallDir356
export PATH=$GEMSTONE/bin:$PATH
export upgradeLogDir=tempDir
```

where *InstallDir356* is the GemStone/S 64 Bit version 3.5.6 installation and *tempDir* is a temporary directory for which you have write permission.

6. Copy extent files

Copy your version 3.4.5 extent files into the location specified by the v3.5.6 configuration file option DBF_EXTENT_NAMES:

- a. Identify the complete set of extent files that are used by your 3.4.5 stone. This can be found by examining the configuration file for the version 3.4.5 repository, looking for the last entry for DBF_EXTENT_NAMES.

- b. The target location is the setting for `DBF_EXTENT_NAMES` in the version 3.5.6 installation. Copy each of these extent files to the target location.

For example:

```
cp InstallDir345/data/extent0.dbf InstallDir356/data
cp InstallDir345/data/extent1.dbf InstallDir356/data
cp InstallDir345/data/extent2.dbf InstallDir356/data
```

Before upgrading, ensure that there are no transaction logs from a previous version of GemStone/S 64 Bit in any of the transaction log locations specified in the configuration file that will be used by version 3.5.6.

Perform the Upgrade

1. Start the Stone

Start the 3.5.6 Stone on the 3.4.5 extents you just copied:

```
unix> startstone stoneName356
```

2. Upgrade image

Ensure you are in a directory to which you have write permission, and run the upgrade script.

The upgrade is performed by the script `upgradeImage`. This script has optional switches to specify the stone name and to set to size of the `GEM_TEMPOBJ_CACHE_SIZE` used for the upgrade process.

```
upgradeImage [-h] [-c cacheSize] [-s stoneName]
```

-h prints this usage information.

-c *cacheSize* sets the size of the `GEM_TEMPOBJ_CACHE_SIZE`; if this is not used, the script will default to use a value of 100000.

-s *stoneName* sets the name of the running stone to upgrade; if this option is not used, the script will default to **gs64stone**.

For example,

```
unix> upgradeImage -s stoneName356
```

The script will prompt you to press the return key to begin.

The script invokes subordinate scripts to complete the upgrade. The upgrade process will take some time. You can examine the progress, if desired, by examining the file `$upgradeLogDir/upgradeImage.out`.

The script should complete with the message:

```
Upgrade completed. No errors detected.
```

If not, please preserve the Stone log file and the contents of `$upgradeLogDir`.

Contact your internal GemStone support person or GemStone Technical Support.

3. Restore System Account passwords

Log in to GemStone/S 64 Bit version 3.5.6 as DataCurator or SystemUser, and change the password for SystemUser, DataCurator, and GcUser to a secure password, such as the passwords used for these accounts in v3.4.5. For example:

```
topaz 1> run
(AllUsers userWithId: 'SystemUser') password: '345Password'.
(AllUsers userWithId: 'GcUser') password: '345Password'.
(AllUsers userWithId: 'DataCurator') password: '345Password'.
System commitTransaction
%
```

where *345Password* is the account password used in version 3.4.5.

GsDevKit Upgrade

If you are using the open-source Development Kit for GemStone/S 64 Bit (GsDevKit, also referred to as Seaside or GLASS), you will need to perform another step to upgrade your GsDevKit image. This step upgrades the GsDevKit base code, and you will also need to reload your application code.

For details, see Chapter 4, starting on page 33.

When you have completed the GsDevKit upgrade, continue with the upgrade process and perform the following steps.

Post-upgrade Application Code Modifications

1. Reinstall any other GemStone products that modify kernel classes.

If you use GemConnect or GemBuilder for Java, you must reinstall the appropriate version of these products into your repository at this time.

To install, use the procedure in the *Installation Guide* for that product.

2. File in Kernel class changes

If you have modified any kernel class methods of the previous version or if you have added methods to kernel classes, carefully compare your changes with the changes in version 3.5.6 to see whether your changes are still necessary or appropriate. Review the *Release Notes* for each intervening version, as well as examining code in the image.

If the kernel class changes are still applicable, file in the changes, verify that errorcount is 0, and commit.

Make Backup

1. Make backup

At this point, you should create a full backup of the upgraded repository.

Configure GCI clients and GBS

1. Recompile User Actions

It is recommended to recompile and relink all User Actions and GCI Applications.

2. Configure GBS

If you are using GBS clients, ensure you are running a supported version of GBS and client Smalltalk. You must use GBS version 8.4 or later for VW, or GBS 5.4.5 or later for VA, to connect to a GemStone/S 64 Bit v3.5.6 repository.

Configure GBS to use the version 3.5.6 client libraries. Depending on the GBS version you are upgrading from, the required libraries, library naming conventions, and the process GBS uses to identify the correct library to load may have changed.

See Chapter 5, 'Configuring GBS for GemStone/S 64 Bit' for details. If your GBS clients run on a different platform than your GemStone server, refer to the *Installation Guide* for that platform.

Upgrading from 3.2x

This chapter describes how to upgrade an existing GemStone/S 64 Bit 3.2.x installation to GemStone/S 64 Bit version 3.5.6. If you are upgrading from version 3.3.x or later, which do not require recompile, see Chapter 2 on page 19. Upgrading from earlier versions requires an intermediate upgrade to version 3.2.x or preferably a later version.

The compiled method bytecodes changed between v3.2 and v3.3, and the upgrade process requires that you file in all application source code so it can be recompiled, and recompile all persistent blocks. Alternatively, you may iterate and recompile all methods in your application.

If you are using GemBuilder for Smalltalk (GBS) or other clients-only nodes in your configuration, you also need to upgrade the client libraries on that node.

You also need to upgrade your version of GBS; versions of GBS earlier than 8.4 or 5.4.5 are not supported with v3.5.6. See Chapter 5 for supported versions of GBS for use with GemStone/S 64 Bit 3.5.6, and instructions on installing updated client libraries.

Keyfiles

New keyfiles are required with GemStone/S 64 Bit version 3.5.6; keyfiles from 3.4.x and earlier are not valid with v3.5.6. To acquire a keyfile for version 3.5.6, email keyfiles@gemtalksystems.com, or contact GemStone Technical Support, preferably providing your existing keyfile.

Keyfiles also manage access to GemConnect and GemBuilder for Java, and the new X509-Secured GemStone feature. If you are using these add-on products, you must use a keyfile with the appropriate permissions.

Upgrade Procedure

The following list summarizes the steps necessary to perform the upgrade to GemStone/S 64 Bit version 3.5.6.

- ▶ Prior to Upgrade in existing application. 26
- ▶ Prepare for Upgrade 27
- ▶ Perform the Upgrade 28
- ▶ Post-upgrade Application Code Modifications. 29
- ▶ Make Backup 32
- ▶ Configure GCI clients and GBS. 32

NOTE

The following instructions use the version number 3.2.16 to refer to the version you are upgrading from, and version number 3.5.6 indicate the target version you are upgrading to. The process is the same when upgrading from any 3.x repository, and upgrading to any 3.2.x versions for which this Installation Guide applies.

Prior to Upgrade in existing application

1. Check for use of deprecated methods

Verify that your application does not invoke any methods that were deprecated in previous releases, by enabling error or logging on deprecation in your existing repository. Deprecated methods are subject to removal in major releases; finding them before upgrading allows the deprecation messages to provide replacement instructions.

For details on finding deprecated methods, refer to the *Programming Guide for GemStone/S 64 Bit*.

2. File out your application code

If you do not already have source code for your application stored externally to the GemStone repository in a code management system, it is recommended to file out all application source code. Filein of application code is used to recompile all methods. You may also write code to manually recompile methods in all classes; see “Recompile application code” on page 30 for details.

You should confirm that the format of your filed out code does not create new versions of your application classes on filein.

GemStone supports multiple versions of the same class, but tools operate on the most recent version of the classes. If you have instance of older versions of your applications classes that have not been migrated to the latest version, these class versions will not be upgraded by filein. We recommend that you migrate all instances to the most recent version of your application classes.

3. File out modifications to GemStone classes

File out any modifications or additions you made to GemStone/S 64 Bit kernel class methods. For more information about fileout, see the *GemStone/S 64 Bit Topaz Programming Environment*.

You will need to carefully compare these changes with GemStone/S 64 Bit 3.5.6 kernel methods, and refer to the *Release Notes* for version 3.3 and all release notes after the version you are upgrading from, to determine whether your changes are still necessary or appropriate. For a listing of Release Notes, see [GemStone/S 64 Bit Release History](#).

CAUTION

Any changes that you have made to the GemStone/S 64 Bit kernel classes will be lost during upgrade; you MUST file these out in order to preserve the changes in version 3.5.6.

Prepare for Upgrade

1. Install and configure GemStone/S 64 Bit 3.5.6

Install GemStone/S 64 Bit 3.5.6 to a new installation directory, separate from the installation directory for version 3.2.16, as described in Chapter 1, starting on page 7. Configure GemStone/S 64 Bit 3.5.6 the way you expect to use it – that is, with the appropriate extent locations and sizes.

If you copy the configuration files from your previous version to the version 3.5.6, be sure to review any changes in configuration parameters to determine if changes are needed.

You should ensure that adequate space is available for extents, transaction logs, and a backup during the upgrade. You must provide space for the extents and transaction logs for both repositories, the old and the new.

2. Reset SystemUser password

Log in to the version 3.2.16 system as a user with OtherPassword privilege, such as DataCurator, and reset the SystemUser password to 'swordfish':

```
topaz 1> printit
(AllUsers userWithId: #SystemUser) password: 'swordfish'.
System commitTransaction.
%
```

The upgrade script logs in with the SystemUser account and the default password, and resets the password for DataCurator and GcUser.

3. Stop user activity

Log in to the version 3.2.16 system as a user with SessionAccess and SystemControl privileges, such as DataCurator, and halt all user activity on the repository.

```
topaz 1> printit
System stopUserSessions.
%
```

4. Shut down the repository

You may now shut down the Stone. The repository must be cleanly shut down to avoid needing recovery when it is restarted with the new version's executables. For example:

```
% stopstone stone3216
```

where *stone3216* is the name of the version 3.2.16 stone on this machine.

5. Set environment variables for version 3.5.6

Set the environment variables required for the upgrade.

```
> export GEMSTONE=InstallDir356
> export PATH=$GEMSTONE/bin:$PATH
> export upgradeLogDir=tempDir
```

where *InstallDir356* is the GemStone/S 64 Bit version 3.5.6 installation and *tempDir* is a temporary directory for which you have write permission.

NOTE

Use a separate log directory for each repository you convert.

6. Copy extent files

Copy your version 3.2.16 extent files into the location specified by the v3.5.6 configuration file option `DBF_EXTENT_NAMES`:

- Identify the complete set of extent files that are used by your 3.2.16 stone. This can be found by examining the configuration file for the version 3.2.16 repository, looking for the last entry for `DBF_EXTENT_NAMES`.
- The target location is the setting for `DBF_EXTENT_NAMES` in the version 3.5.6 installation. Copy each of these extent files to the target location.

For example:

```
> cp InstallDir3216/data/extent0.dbf InstallDir356/data
> cp InstallDir3216/data/extent1.dbf InstallDir356/data
> cp InstallDir3216/data/extent2.dbf InstallDir356/data
```

Before upgrading, ensure that there are no transaction logs from a previous version of GemStone/S 64 Bit in any of the transaction log locations specified in the configuration file that will be used by version 3.5.6.

Perform the Upgrade

1. Start the Stone

Start the 3.5.6 Stone on the 3.2.16 extents you just copied:

```
% startstone stoneName356
```

2. Upgrade image

Ensure you are in a directory to which you have write permission, and run the upgrade script.

The upgrade is performed by the script `upgradeImage`. This script has optional switches to specify the stone name and to set to size of the `GEM_TEMPOBJ_CACHE_SIZE` used for the upgrade process.

```
upgradeImage [-h] [-c cacheSize] [-s stoneName]
```

-h prints this usage information.

-c *cacheSize* sets the size of the `GEM_TEMPOBJ_CACHE_SIZE`; if this is not used, the script will default to use a value of 100000.

-s *stoneName* sets the name of the running stone to upgrade; if this option is not used, the script will default to `gs64stone`.

For example,

```
% upgradeImage -s stoneName356
```

The script will prompt you to press the return key to begin.

The script invokes subordinate scripts to complete the upgrade. The upgrade process will take some time. You can examine the progress, if desired, by examining the file `$upgradeLogDir/upgradeImage.out`.

The script should complete with the message:

```
Upgrade completed. No errors detected.
```

If not, please preserve the Stone log file and the contents of `$upgradeLogDir`. Contact your internal GemStone support person or GemStone Technical Support.

3. Restore System Account passwords

Log in to GemStone/S 64 Bit version 3.5.6 as DataCurator or SystemUser, and change the password for SystemUser, DataCurator, and GcUser to a secure password, such as the passwords used for these accounts in v3.2.16. For example:

```
topaz 1> printit
(AllUsers userWithId: 'SystemUser') password: '3216Password'.
(AllUsers userWithId: 'GcUser') password: '3216Password'.
(AllUsers userWithId: 'DataCurator') password: '3216Password'.
System commitTransaction
%
```

where `3216Password` is the account password used in version 3.2.16.

GsDevKit Upgrade

If you are using the open-source Development Kit for GemStone/S 64 Bit (GsDevKit, also referred to as Seaside or GLASS), you will need to perform another step to upgrade your GsDevKit image. This step upgrades the GsDevKit base code, and you will also need to reload your application code.

For details, see Chapter 4, starting on page 33.

When you have completed the GsDevKit upgrade, continue with the upgrade process and perform the following steps.

Post-upgrade Application Code Modifications

1. Reinstall any other GemStone products that modify kernel classes.

If you use GemConnect or GemBuilder for Java, you must reinstall the appropriate version of these products into your repository at this time.

To install, use the procedure in the *Installation Guide* for that product.

2. File in Kernel class changes

If you have modified any kernel class methods of the previous version or if you have added methods to kernel classes, compare your changes with the changes in version 3.5.6 to see whether your changes are still necessary or appropriate. Carefully review the *Release Notes* for each intervening version, as well as examining code in the image.

If the kernel class changes are still applicable, file in the changes, verify that errorcount is 0, and commit.

3. Recompile application code

The upgrade process requires all executable methods to be recompiled. You should have fileins available, from Step 2. on page 26. Alternatively, you may iterate classes in your image and recompile each one. If you are reusing scripts that managed recompile for the 2.x conversion, verify that the configuration parameter `GemConvertArrayBuilder` is not set.

GsDevKit environments will not need to perform this step; application code reload is done as part of the upgrade described in Chapter 4.

a. Recompile by filein

File in all development and application code. Verify that errorcount is 0, and commit.

If you have instances of previous versions of classes, these old class versions will not be recompiled by this process. You should ensure that all application instances are migrated to current class versions before conversion, or manually recompile instances of older class versions.

b. Recompile within image

To recompile classes without filein, for each class in your repository execute

```
Class recompileAllMethods
```

You should ensure that you do not miss any classes. If you have instance of older versions of your classes, you will need to recompile methods on these older versions. For example:

```
class classHistory do: [:aClassVersion |  
    aClassVersion recompileAllMethods]
```

Recompile is required for 3.2.x methods to be executable in v3.5.6. Attempting to execute methods that have not been recompiled will result in errors.

4. Recompile source code in persistent blocks

The compiled code in persistent blocks also requires recompile before it can be executed. All persistent executable blocks will need to be recompiled as part of upgrading.

c. Application-specific stored blocks

If your application stores persistent blocks, you will have to locate and recompile all such blocks before they can be executed.

d. SortBlocks in SortedCollections

To recompile the sortBlocks in persistent SortedCollections in your application, you may run the `postconv` script. This script only converts simple blocks; if your

SortedCollection blocks are not simple (such as referring to method context), they cannot be automatically recompiled.

```
postconv [-c <numCacheWarmerGems>][-h][-s <stoneName>] [-r]
[-n <numberOfSessions>] [-t <tempObjCacheSize>] [-u <userId>]
```

-c <numCacheWarmerGems> specifies the number of cache warmer threads in a single gem to load the object table into the shared cache before starting post-conversion. If not specified, no cache warming is done.

-h prints this usage information.

-s <stoneName> sets the name of the running stone to scan; if this option is not used, the script uses gs64stone.

-n <numberOfSessions> specifies the number of parallel sessions which will convert the instances of SortedCollection and its subclasses. By default, use one session.

-r specifies to reuse an existing version of \$upgradeLogDir/AllSortedCollections.bms, if it exists. This file contains the OOPs of all instances of SortedCollections and its subclasses. By default, the existing file is deleted and a new one created.

-t <tempObjCacheSize> sets the size of GEM_TEMPOBJ_CACHE_SIZE in KB; by default, 20000.

-u <userId> is the UserId whose SymbolList includes all subclasses of SortedCollection, for which instance's sortBlocks will be converted. If not specified, defaults to SystemUser

For example,

```
% postconv -s stoneName356
```

The postconv script will write progress messages to stdout. When it completes, it will report:

```
postconv[INFO]: Congratulations! NNN SortedCollections were
successfully converted. No errors were detected.
```

If postconv reports errors, the results include information on the specific sortBlocks that failed recompile, such as those for complex sort blocks. These will need manual repair. Contact GemTalk Technical Support for assistance.

5. Resort for ICU-based collation

If the repository has been progressively upgraded through any 3.1.x version, and contains data structures that were built in v3.1.x that depend on ICU collation order or encoding (that is, they involve Unicode strings, or traditional strings if the repository is in Unicode Comparison Mode, including GsDevKit application), then these collections need to be sorted and indexes rebuilt to avoid the (small) risk of lookup failures. If resort/rebuild has been done in 3.2.x or 3.3.x it does not need to be done again.

The ICU libraries that provide Unicode based collation are versioned as the Unicode standard changes. Since most changes in the standard are not important for most applications, by default applications continue to use their original version of ICU library (either the version in which the repository originated, or as determined during upgrade). However, 3.1.x applications used a much older ICU version and cannot be handled automatically.

The version of the ICU shared libraries that will be loaded by session is defined by the global `IcuLibraryVersion`. The `IcuLibraryVersion` after upgrade will be the same as an existing value of `IcuLibraryVersion` before upgrade, and if that key is not present, it is determined based on the originating GemStone version. Details may be in the log file for the `SymbolGem` for the upgrade.

6. Regenerate cached instances of PetitParser classes

Instance of PetitParser classes (classes with names that begin with PP) are not automatically converted to the new class versions. If you are upgrading from v3.2x and using PetitParser classes directly, and you have persistent instances, you should regenerate these instances.

Make Backup

1. Make backup

At this point, you should create a full backup of the upgraded repository.

Configure GCI clients and GBS

1. Recompile User Actions

User Actions and GCI Applications will need to be recompiled and relinked.

2. Configure GBS

If you are using GBS clients, ensure you are running a supported version of GBS and client Smalltalk. You must use GBS version 8.4 or later for VW, or GBS 5.4.5 or later for VA, to connect to a GemStone/S 64 Bit v3.5.6 repository.

Configure GBS to use the version 3.5.6 client libraries. Depending on the GBS version you are upgrading from, the required libraries, library naming conventions, and the process GBS uses to identify the correct library to load may have changed.

See Chapter 5, 'Configuring GBS for GemStone/S 64 Bit' for details. If your GBS clients run on a different platform than your GemStone server, refer to the *Installation Guide* for that platform.

Upgrading GLASS/GsDevKit Applications

This chapter describes the additional upgrade step that applies when upgrading an application that is using variants of the open-source Development Kit for GemStone/S 64 Bit (GsDevKit, referred to also as also as GLASS or Seaside) to GemStone/S 64 Bit v3.5.6. The term GsDevKit is used to collectively refer to any of these environments.

The process described here can be used to upgrade repositories using GLASS, GLASS1, the older GsDevKit environment, and tODE. There are a number of possible configurations and there may be additional setup required for some environments. For more background on these environments, see

https://github.com/GsDevKit/GsDevKit_upgrade/blob/master/README.md#upgrading-glassgsdevkit-applications-to-gemstone-350

If you are using the most recent version, from github.com/GsDevKit/GsDevKit_home, then you may use the upgrade scripts provided there to perform the entire upgrade, rather than using the instructions in this *Installation Guide*.

The complete process for upgrading includes the GemStone standard upgrade, followed by additional GsDevKit upgrade. Upgrading GemStone is described in earlier chapters of this *Installation Guide*; Chapter 2 for version 3.3.x and 3.4.x, and Chapter 3 for upgrade from 3.2.x. You will need to follow the steps in that chapter, which will note the point at which the GsDevKit upgrade takes place.

Upgrade Procedure

The GsDevKit upgrade occurs partway through a standard GemStone upgrade.

To upgrade a GsDevKit/GLASS application:

- First, install the new version of GemStone, and upgrade your repository, according to the instructions in Chapter 2 or Chapter 3.
- After the **upgradeImage** step, you will upgrade the GsDevKit application as described in this chapter.
- After the GsDevKit upgrade completes, continue with the remaining steps of the GemStone upgrade in Chapter 2 or Chapter 3.

1. Ensure that GemStone 3.5.6 is installed and your repository upgraded

You must first follow install version 3.5.6 and follow the instructions in Chapter 2 or Chapter 3, before you can upgrade your GsDevKit application. These instructions will let you know at which point you perform the GsDevKit upgrade.

You should also have confirmed that your application code has been updated as required. We recommend that you install your application code in a test GemStone/S 64 Bit v3.5.6 repository, and verify that your code is working correctly, making changes as necessary. Do this prior to upgrading the data in your application, to ensure the upgrade process will go smoothly.

2. If necessary, customize the upgrade instructions

There are many ways a GsDevKit or GLASS application may be built, and a variety of packages that can be loaded. The **upgradeSeasideImage** script will upgrade a hypothetical standard installation, but there may be customizations required in specific cases.

The upgrade is performed by an upgrade script. By default, this is `$GEMSTONE/upgrade/createGsDevKit_upgrade.topaz`.

The default upgrade script is a file containing topaz commands for the upgrade.

Example 4.1 Default upgrade instructions in `createGsDevKit_upgrade.topaz`

```
run
  UserGlobals
    at: #GsDevKit_Image_Upgrade
      put: (GsuAbstractGsDevKitUpgrade
        upgradeUserName: SeasideUpgradeUser).
  System commitTransaction
%
```

In this script, `SeasideUpgradeUser` is an internal global that by default resolves to `DataCurator`.

Customizing upgrade

To create customized upgrade instructions, make a copy of this file, edit the copy, and pass the path to your customized upgrade script file as an argument to the **upgradeSeasideImage** script.

The following example shows a customized file.

Example 4.2 Example customized upgrade

```

run
UserGlobals
  at: #GsDevKit_Image_Upgrade
  put: ((GsuAbstractGsDevKitUpgrade
        upgradeUserName: 'DataCurator'
        upgradeSymbolDictName: #UserGlobals)
        bootstrapApplicationLoadSpecs: {
          { 'Metacello' .
            'github://dalehenrich/metacello-work:master/repository' } .
          { 'GLASS1' .
            'github://glassdb/glass:master/repository' .
            #( 'default' 'Base' 'Announcements') } .
          { 'Seaside3' .
            'github://SeasideSt/Seaside:master/repository' .
            #( 'CI' ) }
        } ).
System commitTransaction
%
```

Further information about LoadSpecs is provided in the comment for `$GEMSTONE/upgrade/createGsDevKit_upgrade.topaz`.

You may also refer to the example scripts on github, at github.com/GsDevKit/GsDevKit_upgrade/tree/master/bin.

3. Perform the Upgrade

The GsDevKit upgrade is performed by the script **upgradeSeasideImage**, which is located in the `$GEMSTONE/seaside/bin` subdirectory.

Prior to executing **upgradeSeasideImage**, if you need to do a customized upgrade, you should have set up the upgrade script as described above. This is provided a argument to this script.

```

upgradeSeasideImage [ -c tempObjCacheSize ] [ -s stoneName ] [ -u gemstoneUser ]
  [ -p password ] [ -P pathToUpgradeScript ]
-c tempObjCacheSize
  set the size of the GEM_TEMPOBJ_CACHE_SIZE; if omitted, default is 100000.
-s stoneName
  set the name of the running stone to upgrade; if omitted, default is gs64stone.
-u gemstoneUser
  specify the GemStone user name, if seaside was installed as a user other than
  DataCurator. If omitted, defaults to DataCurator.
-p password
  specify the password for gemstoneUser. If omitted, defaults to swordfish.
-P pathToUpgradeScript
  path to customized to GsDevKit_upgrade instance creation script. If omitted,
  $GEMSTONE/upgrade/createGsDevKit_upgrade.topaz.
```

For example,

```
unix> $GEMSTONE/seaside/bin/upgradeSeasideImage -s stoneName356
```

The script will prompt you to press the return key to begin.

The script should complete with the message:

```
Seaside Upgrade completed. No errors detected.
```

4. Load your Application Code

After upgrade has successfully completed, reload your application code.

This should be done for upgrades from 3.3.x and 3.4.x as well as upgrades from 3.2.x.

5. Complete the Upgrade Process

To complete the upgrade, return to Chapter 2 or Chapter 3 and complete the remaining upgrade steps.

Configuring GBS for GemStone/S 64 Bit

The GemStone/S 64 Bit v3.5.6 server requires a compatible version of GBS; versions of GBS earlier than 8.4 are not supported with GemStone/S 64 Bit v3.5.6 or later.

Versions of GemBuilder for Smalltalk (GBS) that are compatible with GemStone/S 64 Bit v3.5.6 do not support Smalltalk client applications running on Solaris, AIX, or Macintosh.

GemStone/S 64 Bit v3.5.6 supports client Smalltalk/GBS applications running with VisualWorks on Linux and Windows, and with VA Smalltalk running on Windows. For a table of all supported GBS and client Smalltalk platforms, see the *GemStone/S 64 Bit Release Notes* for v3.5.6.

For instructions for updating GBS clients that are running on Linux, see the *GemStone/S 64 Bit Installation Guide* for that platform; for GBS clients running on Windows, see the *GemStone/S 64 Bit Windows Client Installation Guide*.