
GemStone®

GemStone/S 64 Bit Installation Guide

for Solaris on Sun SPARC
or x86 _64 Compatible Systems

Version 2.4.5

December 2011

vmware®

GEMSTONE[™]
.....S[™]64

INTELLECTUAL PROPERTY OWNERSHIP

This documentation is furnished for informational use only and is subject to change without notice. VMware, Inc., assumes no responsibility or liability for any errors or inaccuracies that may appear in this documentation.

This documentation, or any part of it, may not be reproduced, displayed, photocopied, transmitted, or otherwise copied in any form or by any means now known or later developed, such as electronic, optical, or mechanical means, without express written authorization from VMware, Inc.

Warning: This computer program and its documentation are protected by copyright law and international treaties. Any unauthorized copying or distribution of this program, its documentation, or any portion of it, may result in severe civil and criminal penalties, and will be prosecuted under the maximum extent possible under the law.

The software installed in accordance with this documentation is copyrighted and licensed by VMware, Inc. under separate license agreement. This software may only be used pursuant to the terms and conditions of such license agreement. Any other use may be a violation of law.

Use, duplication, or disclosure by the Government is subject to restrictions set forth in the Commercial Software - Restricted Rights clause at 52.227-19 of the Federal Acquisitions Regulations (48 CFR 52.227-19) except that the government agency shall not have the right to disclose this software to support service contractors or their subcontractors without the prior written consent of VMware, Inc.

This software is provided by VMware, Inc. and contributors "as is" and any expressed or implied warranties, including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose are disclaimed. In no event shall VMware, Inc. or any contributors be liable for any direct, indirect, incidental, special, exemplary, or consequential damages (including, but not limited to, procurement of substitute goods or services; loss of use, data, or profits; or business interruption) however caused and on any theory of liability, whether in contract, strict liability, or tort (including negligence or otherwise) arising in any way out of the use of this software, even if advised of the possibility of such damage.

COPYRIGHTS

This software product, its documentation, and its user interface © 1986-2011 VMware, Inc., and GemStone Systems, Inc. All rights reserved by VMware, Inc.

PATENTS

GemStone software is covered by U.S. Patent Number 6,256,637 "Transactional virtual machine architecture", Patent Number 6,360,219 "Object queues with concurrent updating", Patent Number 6,567,905 "Generational garbage collector with persistent object cache", and Patent Number 6,681,226 "Selective pessimistic locking for a concurrently updateable database". GemStone software may also be covered by one or more pending United States patent applications.

TRADEMARKS

VMware is a registered trademark or trademark of VMware, Inc. in the United States and/or other jurisdictions.

GemStone, **GemBuilder**, **GemConnect**, and the GemStone logos are trademarks or registered trademarks of VMware, Inc., previously of GemStone Systems, Inc., in the United States and other countries.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Sun, **Sun Microsystems**, and **Solaris** are trademarks or registered trademarks of Oracle and/or its affiliates. **SPARC** is a registered trademark of SPARC International, Inc.

HP, **HP Integrity**, and **HP-UX** are registered trademarks of Hewlett Packard Company.

Intel, **Pentium**, and **Itanium** are registered trademarks of Intel Corporation in the United States and other countries.

Microsoft, **MS**, **Windows**, **Windows XP**, **Windows 2003**, **Windows 7** and **Windows Vista** are registered trademarks of Microsoft Corporation in the United States and other countries.

Linux is a registered trademark of Linus Torvalds and others.

Red Hat and all Red Hat-based trademarks and logos are trademarks or registered trademarks of Red Hat, Inc. in the United States and other countries.

SUSE is a registered trademark of Novell, Inc. in the United States and other countries.

AIX, **POWER5**, and **POWER6** are trademarks or registered trademarks of International Business Machines Corporation.

Apple, **Mac**, **Mac OS**, **Macintosh**, and **Snow Leopard** are trademarks of Apple Inc., in the United States and other countries.

Other company or product names mentioned herein may be trademarks or registered trademarks of their respective owners. Trademark specifications are subject to change without notice. All terms mentioned in this documentation that are known to be trademarks or service marks have been appropriately capitalized to the best of our knowledge; however, VMware cannot attest to the accuracy of all trademark information. Use of a term in this documentation should not be regarded as affecting the validity of any trademark or service mark.

VMware, Inc.
15220 NW Greenbrier Parkway
Suite 150
Beaverton, OR 97006

Preface

About This Documentation

This document explains how to install GemStone/S 64 Bit version 2.4.5, and how to upgrade from previous GemStone/S 64 Bit versions. These release notes are also available on the GemStone Technical Support website.

For information regarding new and modified features, please refer to the *GemStone/S 64 Bit Release Notes*.

Terminology Conventions

The term “GemStone” is used to refer to the server products GemStone/S 64 Bit and GemStone/S; the GemStone Smalltalk programming language; and may also be used to refer to the company, previously GemStone Systems, Inc., now a division of VMware, Inc.

Technical Support

GemStone Website

<http://support.gemstone.com>

GemStone’s Technical Support website provides a variety of resources to help you use GemStone products:

- ▶ **Documentation** for released versions of all GemStone products, in PDF form.
- ▶ **Downloads and Patches**, including past and current versions of GemBuilder for Smalltalk.
- ▶ **Bugnotes**, identifying performance issues or error conditions you should be aware of.
- ▶ **TechTips**, providing information and instructions that are not otherwise included in the documentation.
- ▶ **Compatibility matrices**, listing supported platforms for GemStone product versions.

This material is updated regularly; we recommend checking this site on a regular basis.

Help Requests

You may need to contact Technical Support directly, if your questions are not answered in the documentation or by other material on the Technical Support site. Technical Support is available to customers with current support contracts.

Requests for technical support should be submitted online or by telephone. We recommend you use telephone contact only for serious requests that require immediate attention, such as a production system down. The support website is the preferred way to contact Technical Support.

Website: <http://techsupport.gemstone.com>

Email: techsupport@gemstone.com

Telephone: (800) 243-4772 or (503) 533-3503

When submitting a request, please include the following information:

- ▶ Your name, company name, and GemStone server license number.
- ▶ The versions of all related GemStone products, and of any other related products, such as client Smalltalk products.
- ▶ The operating system and version you are using.
- ▶ A description of the problem or request.
- ▶ Exact error message(s) received, if any, including log files if appropriate.

Technical Support is available from 8am to 5pm Pacific Time, Monday through Friday, excluding VMware/GemStone holidays.

24x7 Emergency Technical Support

GemStone Technical Support offers, at an additional charge, 24x7 emergency technical support. This support entitles customers to contact us 24 hours a day, 7 days a week, 365 days a year, for issues impacting a production system. For more details, contact your GemStone account manager.

Training and Consulting

Consulting is available to help you succeed with GemStone products. Training for GemStone software is available at your location, and training courses are offered periodically at our offices in Beaverton, Oregon. Contact your GemStone account representative for more details or to obtain consulting services.

Chapter 1. Installing GemStone/S 64 Bit Version 2.4.5	7
Review the Installation Procedure	7
Check the System Requirements	8
Prepare for Installation	11
Set the Environment	13
Create the GemStone Key File	14
Verify TCP/IP	14
Define the NetLDI Service	14
Run the Installation Script.	15
Decisions to Make During Installation.	15
Change System Passwords and Set up Users	17
Users must execute gemsetup.	18
Install the default TimeZone	19
What Next?	19
Chapter 2. Upgrading from previous GemStone/S 64 Bit 2.x versions	21
Upgrade Strategy.	21
Upgrade Procedure	21
Prepare for Upgrade	22
Perform the Upgrade.	24
Restore Your Site-Specific Settings and Back Up the Repository	25
Chapter 3. Converting from GemStone/S 6.x	27
Conversion Strategy	28

Conversion Procedure	28
Preprocessing in Old Environment	29
Prepare for Conversion	31
Perform the Conversion and Upgrade	32
Restore Your Site-Specific Settings and Back Up the Repository	35
Detecting Oversize Methods.	36
Chapter 4. Configuring GBS for GemStone/S 64 Bit	37
Supported platforms	38
GemStone/S 64 Bit 2.4.5 Windows Client Installation	39
Installing the GemStone/S 64 Bit 2.4.5 Libraries onto Windows Clients	39
Installing the GemStone/S 64 Bit 2.4.5 Libraries onto Unix Clients	40

Installing GemStone/S 64 Bit Version 2.4.5

This chapter describes the procedure for installing GemStone/S 64 Bit version 2.4.5 on a single machine. If you have enough disk space on a single machine, we recommend that you set up GemStone this way initially to ensure that all the pieces work together. At the end of this chapter, we suggest refinements you might want to make, such as running GemStone in a network configuration.

NOTE

If you are upgrading to this release from a previous version of GemStone/S 64 Bit, or converting from a previous GemStone/S product, follow the instructions in the appropriate chapter of this Installation Guide.

Adjust the installation to meet your specific needs. The topic “What Next?” on page 19 provides references to procedures and related information in the *System Administration Guide for GemStone/S 64 Bit*.

Review the Installation Procedure

The following list summarizes the steps to install GemStone/S 64 Bit.

- ▶ Check the System Requirements 8
- ▶ Prepare for Installation 11
- ▶ Set the Environment 13
- ▶ Create the GemStone Key File 14
- ▶ Verify TCP/IP 14
- ▶ Define the NetLDI Service 14
- ▶ Run the Installation Script 15
- ▶ Change System Passwords and Set up Users 17

Check the System Requirements

Before you install GemStone/S 64 Bit, ensure that the following system requirements are satisfied. Systems meeting these requirements are suitable for installing GemStone/S 64 Bit and beginning development, but additional system resources may be necessary to support large applications.

Platforms

- ▶ Sun SPARC Ultra 1, one CPU, or higher. Your SPARC Ultra must have the V9 instruction set.
- ▶ x86 64-bit system, one 2.6 GHZ PCPU or higher.

RAM

- ▶ At least 1 GB (2 GB recommended)
- ▶ 10 MB for each Gem session process beyond the first two, depending on how the Gem processes are configured

Swap space

- ▶ At least 1 GB of swap space beyond other system needs (2 GB recommended). In general, your total swap space should be at least twice the RAM installed.

Disk space

- ▶ Space for the installed distribution files—you need approximately 450 MB for GemStone/S 64 Bit, and additional space for other products.
- ▶ Additional disk space as required for your repository.
- ▶ The repository files should be located on a disk drive that does not contain swap space. Use of multiple disk drives is advisable for servers.

Operating system

- ▶ Solaris 9 or 10 on SPARC, running a 64-bit kernel, or Solaris 10 on x86.
- ▶ For this release of GemStone/S 64 Bit, the following Solaris patches were installed for the specified Operating System and Platform:

Solaris 9 on SPARC:

kernel version Generic_122300-45, with recommended patches

Solaris 10 on SPARC:

kernel version Generic_141444-09

Solaris 10 on x86:

kernel version Generic_127128-11 or later, with required patches

- ▶ The kernel must be configured to support shared memory and semaphores. See your operating system documentation for further information. These requirements apply both to server nodes and to client nodes (nodes that will run Gem processes).

The following suggested settings in `/etc/system` are typical of those used at GemStone, and most are intentionally set high to provide flexibility. These settings may not be suitable for your hardware configuration and system load.

On Solaris 10, Sun recommends configuring shared memory and semaphores at the project level, rather than system wide. This provides greater flexibility, as well as avoiding the need to reboot after editing `/etc/system`. However, if the parameter settings are present in `/etc/system`, they are used as the default project settings. If you are not partitioning your system using projects, you can continue to configure these settings using `/etc/system`.

a. Shared memory maximum

Solaris 9

`shmsys:shminfo_shmmax` sets the maximum shared memory segment size. The default for maximum shared memory segment is not adequate to run GemStone/S 64 Bit. In the file `/etc/system`, we recommend that the maximum shared memory segment be set to a value larger than your desired Shared Page Cache size, and not more than 75% of your real memory size. For example, if you have 8192 MB of real memory:

```
8192 MB * .75 = 6144 MB
6144 MB * 2**20 = 6442450944 bytes
```

To set this parameter:

```
set shmsys:shminfo_shmmax=6442450944
```

Solaris 10

The equivalent parameter is `project.max-shm-memory`, which controls project total memory use rather than segment size. You may configure this using the `prctl` command on your project. For example, to limit memory to 6 GB:

```
prctl -n project.max-shm-memory -v 6gb -r -i project "user.root"
```

b. Number of semaphore identifiers

Solaris 9

`semsys:seminfo_semmni` sets the number of semaphore identifiers in the system. This parameter limits the number of GemStone shared page caches on the node because each shared page cache uses one identifier. Set this parameter large enough to allow for one shared page cache for each Stone running on the node, plus one for each Stone running on another node, if users log in to that Stone through a Gem session process on the local node.

The Solaris default of 10 should be adequate for most installations.

```
set semsys:seminfo_semmni=10
```

Solaris 10

The equivalent project parameter is `project.max-sem-ids`; the default is 128. This should be adequate for most installations.

c. Maximum number of semaphores per id

Solaris 9

`semsys:seminfo_semmsl` sets the maximum number of semaphores per id (per semaphore set). This parameter limits the number of GemStone sessions that can

log in to a particular Stone and connect to its shared page cache. (Note that `semmsl` ends with a lowercase L, not a digit.)

On the Stone's node, this parameter must provide **two** semaphores for each user who will log in to that Stone from any node plus an overhead of **four**. In distributed systems, nodes that have only user sessions (Gems), but no Stones, must provide **two** semaphores for each user session on that node plus an overhead of **one**.

The Solaris default of 25 is barely adequate for 10 sessions connected to the same Stone, so many installations will require a larger setting. If you increase this setting, you may also need to increase `semsys:seminfo_semmns` (see item on page 10)

The number of semaphores actually requested for a particular shared page cache depends on the GemStone configuration file read by the process that starts the cache and is $(SHR_PAGE_CACHE_NUM_PROCS * 2) + 1$.

To set this parameter:

```
set semsys:seminfo_semmsl=500
```

Solaris 10

The equivalent parameter is `process.max-sem-nsems`. The default is 512 which is adequate for moderately sized systems. For larger systems,

```
prctl -n project.max-sem-nsems -v 1024 -r -i project "user.root"
```

d. Total number of semaphores

Solaris 9

`semsys:seminfo_semmns` sets the total number of semaphores in the system. This parameter limits the total number of GemStone sessions on a node.

The default of 60 may not be adequate for some GemStone installations, especially if other software uses semaphores or if more than one shared page cache will be present. Ensure that this `semmns` \geq `semmsl` (see item on page 9).

To set this parameter:

```
set semsys:seminfo_semmns=640
```

Solaris 10

This parameters has been removed in Solaris 10.

- e. If you are adjusting settings using `/etc/system`, save the file, and reboot the system using `boot -r`.
- ▶ The configuration option `SHR_PAGE_CACHE_SIZE_KB` defines the size (in KBytes) of extent page space in the shared page cache. The maximum acceptable value for this configuration option is limited by system memory, kernel configurations, and cache space allocated by `SHR_PAGE_CACHE_NUM_PROCS`.

For more general information about these and other configuration options, see Appendix A of the *System Administration Guide for GemStone/S 64 Bit*.

System clock

- ▶ The system clock must be set to the correct time. When GemStone opens the repository at startup, it compares the current system time with the recorded checkpoint times as part of a consistency check. A system time earlier than the time at which the last checkpoint was written may be taken as an indication of corrupted data and prevent GemStone from starting. The time comparisons use GMT.

TCP keepalive option

- ▶ GemStone processes ordinarily use the TCP `keepalive` option to determine how long they will wait after communications activity ceases unexpectedly. This setting can be useful for reaping stale RPC Gems, but the operating system default may not be appropriate for this purpose. For further information, refer to your operating system documentation.

C/C++ Compiler

SPARC:

- ▶ CC: Sun C++ 5.8 Patch 121017-05 2006/08/30

x86:

- ▶ CC: Sun C++ 5.8 Patch 121018-20 2009/04/20

GemStone requires a C/C++ compiler only if you are developing C or C++ code for user actions or for a C or C++ application. This compiler is required only for development work, not for execution.

Debugger

SPARC:

- ▶ Sun Dbx Debugger 7.5 Patch 121023-02 2006/05/26

x86:

- ▶ Sun Dbx Debugger 7.5 Patch 121616-06 2008/01/24

A C debugger can be useful to allow problem analysis by GemStone consulting or Technical Support. It also may allow you to debug your C user actions. It is not required for GemStone execution.

Prepare for Installation

Perform the following steps to prepare the machine to receive the GemStone/S 64 Bit software. Although most steps require root login, we recommend that you perform the initial step as the GemStone administrator.

These are the portions of the system that are affected by the installation of GemStone:

`/dev/rdisk`

Optional raw partitions for repository extents and transaction logs

`/etc/services`

Internet services database

`/InstallDir/GemStone64Bit2.4.5-sparc.Solaris`

`/InstallDir/GemStone64Bit2.4.5-i386.Solaris`

Location of the object server software

`/opt/gemstone`

Default location for server lock files, and log files for GemStone network servers (NetLDIs)

`/tmp/gemstone`

Pipe file for the Stone repository monitor

`/usr/gemstone`

Alternative location for lock and log files, for compatibility with previous products; `/opt/gemstone` is created unless `/usr/gemstone` already exists

1. As the GemStone administrator, log in to a machine that has adequate resources to run GemStone and that owns the disk on which you are going to install the GemStone files.

NOTE

Do not copy the files as root. The ownerships that were in effect when the distribution media was created are preserved, and this might result in file permission errors for users at your site.

2. Determine that adequate swap space is available:

```
% /usr/sbin/swap -s
```

3. Check the free disk space and determine the disk drive and partition on which you will install the GemStone software.

To list all disk partitions, along with the amount of free space in each partition:

```
% df
```

We recommend that you avoid choosing either an NFS-mounted partition or one containing UNIX swap space for the initial installation. Mounted partitions can result in executables running on the wrong machine and in file permission problems. Existence of swap space on the same drive can dramatically slow GemStone disk accesses.

4. Select an installation directory, *InstallDir*, and make this directory the current working directory.
5. GemStone/S 64 Bit is provided as a zipped archive file with a name similar to `GemStone64Bit2.4.5-sparc.Solaris.zip` or `GemStone64Bit2.4.5-i386.Solaris.zip`. Move this distribution file to the directory location in which GemStone will be installed, *InstallDir*.
6. Unzip the distribution file using `unzip`. For example:

```
% unzip GemStone64Bit2.4.5-sparc.Solaris.zip
```

The *InstallDir* now contains a GemStone directory with a name similar to `GemStone64Bit2.4.5-sparc.Solaris` or `GemStone64Bit2.4.5-i386.Solaris`.

In addition to several subdirectories, this directory also contains two text files: `PACK-ING`, which lists all of the GemStone files, and `version.txt`, which identifies this particular product and release of GemStone.

7. Log in as root.

NOTE

Although you can complete the installation as a non-root user, we do not

*recommend this. During installation, GemStone system security is established through file permissions and process attributes. To ensure that the installation is successful, **you must install as root**. If you later decide to change the security of your GemStone system, see Chapter 1 of the System Administration Guide for GemStone/S 64 Bit, which explains the concept of GemStone server file permissions and how to change them.*

Set the Environment

Perform the following steps to properly configure the operating environment.

1. Set the environment variable GEMSTONE.
 - a. If more than one installation of any GemStone/S product resides on this machine, check for existing GemStone environment variables:

```
% env | grep GEM
```

All GemStone environment variables are displayed.

- b. If any environment variables exist, you must specifically unset each one.

C shell:

```
% unsetenv GEMSTONE GEMSTONE_SYS_CONF \  
GEMSTONE_EXE_CONF GEMSTONE_LOG GEMSTONE_LANG
```

Bourne or Korn shell:

```
$ unset GEMSTONE GEMSTONE_SYS_CONF GEMSTONE_EXE_CONF \  
GEMSTONE_LOG GEMSTONE_LANG
```

- c. Set the environment variable GEMSTONE to the *full pathname* (starting with a slash) of your new GemStone installation directory.

C shell:

```
% setenv GEMSTONE InstallDir/GemStone64Bit2.4.5-sparc.Solaris
```

or

```
% setenv GEMSTONE InstallDir/GemStone64Bit2.4.5-i386.Solaris
```

Bourne or Korn shell:

```
$ GEMSTONE=InstallDir/GemStone64Bit2.4.5-sparc.Solaris  
$ export GEMSTONE
```

or

```
$ GEMSTONE=InstallDir/GemStone64Bit2.4.5-i386.Solaris  
$ export GEMSTONE
```

Create the GemStone Key File

To run GemStone, you must create a key file. Instructions and information to create this file were shipped with the distribution media. If either of these materials is missing, call GemStone Contract Administration.

1. Change the permissions on the directory `$GEMSTONE/sys` so that you can create the file:

```
% cd $GEMSTONE/sys
% chmod 755 .
```

2. Using a text editor and the information provided, create the key file `$GEMSTONE/sys/gemstone.key`.

3. Change the file and directory permissions so that they are no longer writable:

```
% chmod 555 gemstone.key
% chmod 555 .
```

Verify TCP/IP

To run GemStone, TCP/IP must be functioning, even if your machine is not connected to a network.

1. Verify that TCP/IP networking software is functioning (each **1** is the number 1):

```
% /usr/sbin/ping hostname 1 1
```

where *hostname* is the name of your machine. If **ping** responds with *hostname is alive*, TCP/IP is functioning.

Define the NetLDI Service

The NetLDI service, by default `gs64ldi`, should be defined in your TCP/IP network database. This is required for certain kinds of local sessions, or any client on a remote machine, to log into GemStone. For clients on remote machines, the same NetLDI service name and port number must be defined on the remote machine.

NOTE

If you are upgrading from a previous version, you might need to keep the NetLDI for that version running. You may need to select a distinct name and port for the NetLDI for GemStone/S 64 Bit 2.4.5, rather than using the default `gs64ldi`.

1. Determine whether the `gs64ldi` service is already defined:

```
% ypcat services | grep gs64ldi
```

If it is defined, skip the rest of this procedure and continue with the installation at “Run the Installation Script” on page 15.

If it is not defined, continue performing this procedure.

2. Determine which TCP/IP network database (local or NIS) is in use:

```
% ypwhich
```

If the program is missing or you see an error message when you run it, you can assume that your machine is using a local copy of the TCP/IP network database instead of a copy provided by NIS. Perform the following step on your local copy of the network database (the file `/etc/services`).

If NIS is running, have your UNIX system administrator perform the following steps.

3. Add an entry similar to the following to the network database:

```
gs64ldi 50377/tcp #GemStone/S 64 Bit 2.4.5
```

Choose a port number that is not being used by another service. The port number should be in the range `49152 <= port <= 65535`, to conform to IANA standards (<http://www.iana.org/assignments/port-numbers>).

4. If NIS is running, propagate the change to the network database to the rest of the network.
5. If NIS is not running, but several machines will be running GemStone, have the UNIX system administrator update the network database for each machine. Note that the port number must be the same for every machine.

Run the Installation Script

Invoke the installation script from the `install` subdirectory:

```
% cd $GEMSTONE/install
% ./installgs
```

`installgs` is an interactive script that analyzes your system configuration and makes suggestions to guide you through installing GemStone on your machine.

NOTE

You can usually terminate execution of the installation script with Ctrl-C without risk to your files. When it is not safe to do so, the message `Please do not interrupt` appears on the screen. If this happens, wait for the message `now it is OK to interrupt` before you interrupt the script. You can run the script again from the beginning as many times as necessary.

Decisions to Make During Installation

During installation, you are asked several questions. The entire installation dialog is not reproduced here, but the main points are addressed. Some questions may not be asked, depending on answers to previous questions.

Whenever you are asked to answer “yes” or “no,” answer with **y** or **n**. When the script offers a default answer in square brackets (such as “[y]”), press Enter to accept the default.

Do you want the installation script to set up directories for server lock files and NetLDI logs?

The default location for server lock files and NetLDI log files is `/opt/gemstone`, although for compatibility with earlier products `/usr/gemstone` is used only if it exists. If the environment variable `GEMSTONE_GLOBAL_DIR` is defined to point to a valid directory, this overrides the default server lock files and log file location; however, all

Gemstone processes that will interact on this machine must have this environment variable set to the same directory.

If these directories do not exist, the installation script offers to create `/opt/gemstone` and the subdirectories `locks` and `log`. Then, the script offers to set access (770) to these directories.

If you answer **no** to creating the directories, you must create them (or provide a symbolic link) before starting the server.

Do you want the installation script to set the owner and group for all the files in the GemStone distribution?

If you answer **yes**, the script will prompt you for the owner and group you want to use. Refer to Chapter 1 of the *System Administration Guide for GemStone/S 64 Bit* for more information about setting owner and group permissions.

If you answer **no**, the permissions will remain the same as when the files were extracted from the distribution media.

Do you want the installation script to protect the repository file?

The default, which we recommend, gives only the owner read and write access (600) through ordinary UNIX commands. Other users can read and write the repository through a GemStone session. If you choose not to protect the repository, the setuid bit is cleared from all executables, which causes them to run under ownership of the user who invokes them.

Default: Set the repository permission to 600, and leave the setuid bit applied.

Allow NetLDI to Run as Root?

Do you want the installation script to allow non-root users to start a NetLDI that runs as root?

The NetLDI is a network server that permits remote processes to interact with the repository. There are two ways to set up a NetLDI so that it can provide services to all GemStone users: it can run as root, or it can run in guest mode with a captive account.

- ▶ To run NetLDIs as root, accept the default “yes” response. Ownership of the NetLDI executable is changed to root, and the setuid bit is set. Any GemStone user will be able to start a NetLDI process that is accessible to all GemStone users because it will always run as root. For certain services, users will need to authenticate themselves by supplying a password. Alternatively, answer “no” but log in as root before starting the NetLDI.

If the NetLDI uses a port number less than 1024, it must run as root.

- ▶ To run NetLDIs in guest mode with a captive account, answer “no” to the prompt, because those modes are not permitted if the NetLDI runs as root. “Guest mode” means that GemStone users do not have to supply a UNIX password to use NetLDI services. The “captive account” is an account that owns all processes the NetLDI starts; typically, it is the GemStone administrative account that owns the files. You must start the NetLDI while logged in as that account.

Default: Change ownership of the `netldi` executable to root, and set its setuid bit.

Set up an Extent?

Do you want the installation script to set up an extent now?

GemStone is distributed with a read-only copy of the initial repository in `$GEMSTONE/bin/extent0.dbf`. Before you can start GemStone, this file must be copied to a suitable location and made writable. The script offers to copy the file to its default location of `$GEMSTONE/data`.

If you are a new GemStone user, we recommend that you answer **y**. If you are an existing GemStone user, you might prefer to answer **n**, then copy the extent to a different location yourself. (If you choose a location other than the default, you must edit your configuration file before starting GemStone. For information, see the *System Administration Guide for GemStone/S 64 Bit*.)

Default: Place a writable copy of `extent0.dbf` in `$GEMSTONE/data`.

Start a NetLDI?

Do you want the installation script to start a NetLDI?

If you prefer, you can start these processes manually at any time.

Almost every host needs a NetLDI. You must start a NetLDI when the Stone repository monitor or Gem session processes will run on this machine.

You can start a NetLDI that runs as root by answering **yes** to this prompt and the confirmation that follows. However, if you want to start the NetLDI in guest mode with a captive account, you must do that after completing the installation. For more information about guest mode with captive account, see Chapter 3 of the *System Administration Guide for GemStone/S 64 Bit*.

Default: Do not start a NetLDI at this time.

Start an Object Server?

As root, you cannot start an object server, but the script offers to start one as another user. You will start the server later in the installation, so answer **no**.

Default: Do not start an object server at this time.

Log out as root

Log out as user root. The rest of the installation is done as the GemStone administrative user.

Change System Passwords and Set up Users

After installing GemStone/S 64 Bit, you must change the passwords for the three administrative users: DataCurator, SystemUser, and GcUser. (The initial password for each is `swordfish`.) The DataCurator account is used to perform system administration tasks. The SystemUser account ordinarily is used only for performing GemStone system upgrades. The GcUser account is used by the garbage collection task, which runs automatically as a separate login. Access to each of these accounts should be restricted.

You must also establish GemStone accounts for each of your system's users.

The chapter entitled User Accounts and Security in the *System Administration Guide for GemStone/S 64 Bit* tells you how to change the passwords and set up accounts for other GemStone users, and how to create new GemStone users accounts. These functions can also be done using GemBuilder for Smalltalk tools; see the *GemBuilder for Smalltalk Users's Guide* for more information.

Users must execute gemsetup

The directory `$GEMSTONE/bin` contains two files, `gemsetup.sh` and `gemsetup.csh`, to help set a user's environment. These files define the GemStone environment for users by modifying the `PATH` and `MANPATH` variables to include `$GEMSTONE/bin` and `$GEMSTONE/doc`, respectively.

After GemStone/S 64 Bit 2.4.5 has been installed, you should notify each GemStone user of the installation and explain how to use the `gemsetup` files.

NOTE

This procedure applies to users ONLY. Each user must perform this procedure before running GemStone.

1. Set the environment variable `GEMSTONE` to the *full pathname* (starting with a slash) of the GemStone/S 64 Bit 2.4.5 directory.

C shell:

```
% setenv GEMSTONE InstallDir/GemStone64Bit2.4.5-sparc.Solaris
```

or:

```
% setenv GEMSTONE InstallDir/GemStone64Bit2.4.5-i386.Solaris
```

Bourne or Korn shell:

```
$ GEMSTONE=InstallDir/GemStone64Bit2.4.5-sparc.Solaris
```

```
$ export GEMSTONE
```

or:

```
$ GEMSTONE=InstallDir/GemStone64Bit2.4.5-i386.Solaris
```

```
$ export GEMSTONE
```

2. Invoke the script `gemsetup`.

C shell:

```
% source $GEMSTONE/bin/gemsetup.csh
```

Bourne or Korn shell:

```
$ . $GEMSTONE/bin/gemsetup.sh
```

3. If you will use GemStone frequently, consider adding to your login shell's initialization file (`.cshrc` or `.profile`) the environment variable `GEMSTONE` and the command `gemsetup`. This way, the GemStone environment is automatically configured every time you log in or create a login shell. It overrides any other GemStone path settings.

NOTE

If you use the Korn shell and your `.profile` contains commands that are not POSIX-compliant, you might encounter errors when a shell is initialized. To remedy this situation, place the non-compliant commands within a conditional, such as the following:

```
hash -r 2>/dev/null
status=$?
if [ $status -ne 0 ]; then
    # Place Korn-shell-specific initialization here
fi
```

Install the default TimeZone

GemStone/S 64 Bit is shipped with a default time zone of US Pacific. If you are in another Time Zone, edit the file `installtimezone.txt` in the GemStone upgrade directory, then file it in as SystemUser.

What Next?

This chapter has guided you through installation of GemStone/S 64 Bit 2.4.5 in an initial configuration that is sufficient to create a basic repository and begin setting up user accounts. The objective has been to get a simple, default configuration up and running.

You might consider performing the following tasks:

- ▶ To modify the initial object server configuration to one that is more efficient for your particular needs, refer to Chapter 1 of the *System Administration Guide for GemStone/S 64 Bit*. This chapter contains sample configurations, from small to large, and also contains detailed information about how to tailor these configurations to your own system.
- ▶ To modify the configuration of Gem session processes and to ensure that users have the necessary permissions to access the shared page cache and the extents, refer to Chapter 2 of the *System Administration Guide for GemStone/S 64 Bit*.
- ▶ If you are going to operate in a network environment, Chapter 3 of the *System Administration Guide for GemStone/S 64 Bit* has additional information about the GemStone network server (NetLDI), how to handle user authentication, how to share software over the network, and how to set up some common configurations.
- ▶ To start and stop the GemStone object server, refer to instructions in Chapter 4 of the *System Administration Guide for GemStone/S 64 Bit*.

Upgrading from previous GemStone/S 64 Bit 2.x versions

This chapter describes how to upgrade an existing GemStone/S 64 Bit 2.x installation to GemStone/S 64 Bit version 2.4.5. GemStone/S 64 Bit version 2.4.5 supports upgrade from GemStone/S 64 Bit versions 2.2.x (2.2.5 or later), and all version of 2.3.x and 2.4.x.

If you are upgrading from 32-Bit GemStone/S, which requires conversion, see the appropriate chapter for conversion instructions.

If you are using GemBuilder for Smalltalk (GBS), you should also upgrade the client libraries that are used by GBS. See Chapter 4 for supported versions of GBS for use with GemStone/S 64 Bit 2.4.5, and instructions on installing updated client libraries.

For applications using GemConnect or Gembuilder for Java, these products will need to be reinstalled following the upgrade process.

Upgrade Strategy

We recommend that you perform the upgrade twice: first a pilot upgrade and then the production upgrade. With this strategy, you can keep your production system running while you familiarize yourself with the upgrade process.

Upgrade Procedure

The following list summarizes the steps necessary to perform the upgrade to GemStone/S 64 Bit version 2.4.5.

- ▶ Prepare for Upgrade..... 22
- ▶ Perform the Upgrade 24
- ▶ Restore Your Site-Specific Settings and Back Up the Repository 25

NOTE

The following instructions use the version number 2.4.4.7 to represent any version from which upgrade is supported. The procedure is the same regardless of which version you have.

Prepare for Upgrade

Perform the following steps to prepare for the upgrade.

1. File out any modifications or additions you made to GemStone/S 64 Bit kernel class methods by using the Topaz command **fileout**. For more information about fileout, see the *GemStone Topaz Programming Environment*.

You will need to carefully compare these changes with GemStone/S 64 Bit 2.4.5 kernel methods to determine whether your changes are still necessary or appropriate.

2. If you are upgrading from version 2.1.x or 2.2.x, you must remove all indexes in your application. There are changes in the indexing internal structures to accommodate QuadByteStrings, introduced in v2.3, and these structures for existing indexes are not modified by upgrade.
3. Install GemStone/S 64 Bit 2.4.5 to a new installation directory, separate from the installation directory for version 2.4.4.7, as described in Chapter 1 of this Installation Guide.
4. Configure GemStone/S 64 Bit 2.4.5 the way you expect to use it – that is, with the appropriate extent locations and sizes.
5. Ensure that adequate space is available for extents, transaction logs, and a backup during the upgrade:

⌘ **df**

You must provide space for the following:

- ▶ Your version 2.4.4.7 extents and transaction logs.
- ▶ Your version 2.4.5 extents and transaction logs.

6. Log in to the version 2.4.4.7 system and reset the SystemUser password to 'swordfish':

```
topaz 1> printit
(AllUsers userWithId: #SystemUser) password: 'swordfish' .
System commitTransaction .
⌘
```

The upgrade script logs in with the SystemUser account and the default password.

7. Halt all user activity on the repository you are going to upgrade:
 - a. Log in to Topaz as DataCurator.
 - b. Force all other users off the system:

```
topaz 1> printit
System stopUserSessions.
⌘
```

CAUTION

You **MUST** file out any changes that you have made to the GemStone/S 64 Bit kernel classes in order to preserve these changes in version 2.4.5. Also, consider saving important modified files, such as configuration files, that will be overwritten during the upgrade.

8. File out any modifications or additions you made to GemStone/S 64 Bit version 2.4.4.7 kernel class methods by using the Topaz command **fileout**. For more information about fileout, see the *GemStone/S 64 Bit Topaz Programming Environment*.

9. You must now shut down the Stone:

```
% stopstone stone2447
```

where *stone2447* is the name of the version 2.4.4.7 stone on this machine. The repository must be cleanly shut down before it can be restarted under version 2.4.5

10. Set up the version 2.4.5 environment.

Set the environment variables required for the upgrade.

C shell:

```
% setenv GEMSTONE InstallDir245
% set path = ($GEMSTONE/bin $path)
% setenv upgradeLogDir tempDir
```

Bourne or Korn shell:

```
$ GEMSTONE=InstallDir245
$ export GEMSTONE
$ export PATH=$GEMSTONE/bin:$PATH
$ upgradeLogDir=tempDir
$ export upgradeLogDir
```

where *InstallDir245* is the GemStone/S 64 Bit version 2.4.5 installation and *tempDir* is a temporary directory for which you have write permission.

NOTE

Use a separate log directory for each repository you convert. A repository may contain multiple extents.

11. Copy your version 2.4.4.7 extent files into the location specified by the configuration file option `DBF_EXTENT_NAMES`:
 - a. Using a text editor, open the configuration file that the version 2.4.4.7 repository uses.
 - b. Locate the last occurrence of the option `DBF_EXTENT_NAMES`, and note its value, a list of `.dbf` files.
 - c. Copy each `.dbf` file to the noted location in the version 2.4.5 installation. For example:

```
% cp InstallDir2447/data/extent0.dbf 245location
% cp InstallDir2447/data/extent1.dbf 245location
% cp InstallDir2447/data/extent2.dbf 245location
```

where *245location* is the location specified by `DBF_EXTENT_NAMES` in the configuration file that will be used in version 2.4.5.

- Before upgrading, ensure that there are no transaction logs from a previous version of GemStone/S 64 Bit in any of the transaction log locations specified in the configuration file that will be used by version 2.4.5. Transaction logs from earlier versions are not compatible with version 2.4.5. If the transaction log directories will be reused for version 2.4.5, any transaction logs should be deleted or copied elsewhere.

Perform the Upgrade

- Start the 2.4.5 Stone on the 2.4.4.7 extents you just copied:

```
% startstone stoneName245
```

- Ensure you are in a directory to which you have write permission, and run the upgrade script.

The upgrade is performed by the script `upgradeImage`. This script has optional switches to specify the stone name and to set to size of the `GEM_TEMPOBJ_CACHE_SIZE` used for the upgrade process.

```
upgradeImage [-h] [-c <cacheSize>] [-s <stoneName>]
```

`-h` prints this usage information.

`-c <cacheSize>` sets the size of the `GEM_TEMPOBJ_CACHE_SIZE`; if this is not used, the script will default to use a value of 100000.

`-s <stoneName>` sets the name of the running stone to upgrade; if this option is not used, the script will default to **gs64stone**.

For example,

```
% upgradeImage -s stoneName245
```

The script will prompt you to press the return key to begin.

- The script invokes subordinate scripts to complete the upgrade. The upgrade process will take some time. You can examine the progress, if desired, by examining the file `$GEMSTONE/upgradeImage.out`.

The script should complete with the message:

```
Upgrade completed. No errors detected.
```

If not, please preserve the Stone log file and the contents of `$upgradeLogDir`. Contact your internal GemStone support person or GemStone Technical Support.

- If you are using Seaside/GLASS, the upgrade is performed by the script `upgradeSeasideImage`. Do not run this script if your version 2.4.4.7 repository did not have Seaside installed.

```
upgradeSeasideImage [-c <tempObjCacheSize>] [-s <stoneName>]
```

`-s <stoneName>` sets the name of the running stone to upgrade; if this option is not used, the script will default to **gs64stone**.

`-c <cacheSize>` sets the size of the `GEM_TEMPOBJ_CACHE_SIZE`; if this is not used, the script will default to use a value of 100000.

For example,

```
% $GEMSTONE/seaside/bin/upgradeSeasideImage -s stoneName245
```

The script will prompt you to press the return key to begin.

Restore Your Site-Specific Settings and Back Up the Repository

1. Reinstall any other GemStone products that modify kernel classes.
If you use GemConnect, you must install it again at this time. Use the procedure in the installation guide for this product.
2. Log in to GemStone/S 64 Bit version 2.4.5 as DataCurator.
3. Change the password for SystemUser, which you changed to `swordfish` prior to the conversion, back to its previous value. Also, change the passwords for GcUser and DataCurator, which were reset by the conversion process, back to the version 2.4.4.7 value:

```
topaz 1> printit
(AllUsers userWithId: 'SystemUser') password: '2447Password' .
(AllUsers userWithId: 'GcUser') password: '2447Password' .
(AllUsers userWithId: 'DataCurator') password: '2447Password' .
System commitTransaction
%
```

where `2447Password` is the account password used in GemStone/S 64 Bit version 2.4.4.7.

The upgraded repository is now usable. Other users can log in to assist with the following steps.

4. If you have modified any kernel class methods of the previous version, carefully compare your changes with version 2.4.5 kernel methods to see whether your changes are still necessary or appropriate. If so, file in the changes and commit.
5. Create a full backup of the upgraded repository. For details, see the *System Administration Guide for GemStone/S 64 Bit*.
6. If you are using GBS clients, configure these to use the version 2.4.5 client libraries. See Chapter 4, 'Configuring GBS for GemStone/S 64 Bit' for details.

Converting from GemStone/S 6.x

This chapter describes how to convert an existing GemStone/S installation to GemStone/S 64 Bit version 2.4.5. GemStone/S 64 Bit version 2.4.5 supports upgrade from GemStone/S version 6.5.2 or later. If you are converting from 6.1.x, you must first upgrade to version 6.5.2 or later, before converting to GemStone/S 64 Bit version 2.4.5.

While GemStone/S is similar to GemStone/S 64 Bit, there are differences in code and administration. Conversion to GemStone/S 64 Bit requires modifications to your existing application.

As part of the conversion process, you:

- ▶ Modify classes and methods that run in GemStone so they work properly with the GemStone/S 64 Bit classes and methods.
- ▶ Modify your application's client code as necessary. This code may be in C, C++, or client Smalltalk.

NOTE

In order to use GemBuilder for Smalltalk (GBS) with the GemStone/S 64 Bit v2.4.5 server, you may need to upgrade your GBS version, and configure it correctly for use with GemStone/S 64 Bit. See the supported versions and configuration instructions in Chapter 4 of this Installation Guide.

- ▶ Ensure you have no methods whose compiled size is larger than 64K. Methods larger than 64K will not fail during conversion, but cannot be loaded or executed in GemStone/S 64 Bit. For more information, see "Detecting Oversize Methods" on page 36.
- ▶ File out the changes to GemStone kernel classes.
- ▶ Convert and upgrade your repository in a multi-stage process per the instructions starting on page 29.
- ▶ File in your GemStone kernel class changes.
- ▶ Recompile and relink any C user actions or client applications.

- ▶ Recompile and relink any C or C++ user actions or client applications.
- ▶ Reload client Smalltalk images.

The architecture of the repository in GemStone/S 64 Bit 2.4.5 is substantially different from GemStone/S 6.x. For that reason, the upgrade from v6.x to v2.4.5 is a conversion that cannot be done in place. The upgrade conversion process will construct a new GemStone/S 64 Bit repository, using the 6.x repository as a template. When the conversion is completed, both the 6.x and 2.4.5 repositories will exist. This means that enough disk space must be available to accommodate both repositories.

The GemStone/S 64 Bit 2.4.5 repository will be substantially larger than the GemStone/S 6.x repository. Repository size increases between 20% and 200% or more are likely, depending on the nature of the data in the repository.

The conversion process will not substantially modify the original 6.x repository. The 6.x repository will remain in a fully usable and coherent state after the conversion is completed.

Conversion Strategy

We recommend that you perform the upgrade conversion twice: first a pilot conversion and then the production conversion. With this strategy, you can keep your version 6.x production system running while you familiarize yourself with the conversion process. The steps are the same for the pilot and the production conversions; where there are difference, this is noted in the instructions.

If possible, the pilot conversion should be done on a copy of your production system. During the pilot conversion, the database integrity is verified before and after conversion, and growth information on the repository is determined that will allow you to configure the final version 2.4.5 system correctly.

Conversion Procedure

The conversion procedure from GemStone/S 6.x to GemStone/S 64 Bit 2.4.5 is performed in several stages. The first stage executes in the existing 6.x environment, that is, with \$GEMSTONE pointing to the GemStone/S v6.x product tree. Do not reset \$GEMSTONE until specified in the instructions. The following phases of conversion execute in the GemStone/S 64 Bit environment.

The following list summarizes the steps necessary to perform the conversion to GemStone/S 64 Bit v2.4.5.

- ▶ Preprocessing in Old Environment3-29
- ▶ Prepare for Conversion3-31
- ▶ Perform the Conversion and Upgrade3-32
- ▶ Restore Your Site-Specific Settings and Back Up the Repository3-35

Preprocessing in Old Environment

1. File out any modifications or additions you made to GemStone/S kernel class methods by using the Topaz command **fileout**. For more information about fileout, see the *GemStone Topaz Programming Environment*.

You will need to carefully compare these changes with GemStone/S 64 Bit 2.4.5 kernel methods to determine whether your changes are still relevant or appropriate.

2. Verify that you have no methods larger than 64K. This must be done prior to conversion. Oversize methods do not cause an error in the conversion, but cannot be loaded or executed in the converted repository. GemStone/S 64 Bit 2.4.5 provides a tool to assist in detecting oversize methods - see "Detecting Oversize Methods" on page 3-36
3. Install GemStone/S 64 Bit 2.4.5 to a new installation directory, separate from the installation directory for 6.x, as described in Chapter 1 of this Installation Guide.

Define a new environment variable, `$GEMSTONE_64`, to point to this product tree. At this point, do not reset `$GEMSTONE` or update the path to point to v2.4.5.

For example, using the default GemStone/S 64 Bit 2.4.5 installation location from Chapter 1:

C shell:

```
% setenv GEMSTONE_64 <InstallDir>/GemStone64Bit2.4.5-<platform>
```

Bourne or Korn shell:

```
$ GEMSTONE_64=<InstallDir>/GemStone64Bit2.4.5-<platform>
$ export GEMSTONE_64
```

4. Check the system configuration file used by your existing version 6.x installation. If the environment variable `$GEMSTONE` is used in the paths for extent file locations in the `DBF_EXTENT_NAMES`, this must be changed to use the absolute path. The conversion will not proceed with `$GEMSTONE` in the extent file path/s.
5. If this is the pilot conversion, to verify the integrity of your v6.x system, run an object audit and a page audit prior to conversion. For the page audit, which requires the stone to be shut down, you may choose to run this following the **convprep6x** step (step 13 on page 31).

For instructions in running object and page audits, see the *System Administration Guide*.

6. Prior to conversion, ensure there are no dead objects in your repository.
7. Optional: Set up classes for list instances.

Some customers may need to perform application level object conversions on their repository, after the GemStone conversion has completed. For such applications, GemStone can be instructed to create lists of instances of particular classes during conversion. This behavior is not enabled by default. To enable, you must define a UserGlobal with a specific name and structure. Collecting the lists of instances will slow down the conversion process; larger numbers of classes and instances of these classes will slow down the conversion more.

To collect lists of instance of classes, before invoking the **convprep6x** script, do the following:

- a. Determine the list of classes for which instances are to be collected by the conversion.
- b. Login to the v6.x system as SystemUser and ensure you are in transaction.
- c. Create an IdentitySet containing one of more classes for which instances are to be located.
- d. Store the IdentitySet in UserGlobals under the key #ConversionClassesToFind.
- e. Commit the transaction.

During the execution of the **convprep6x** script, if the symbol #ConversionClassesToFind is found, information is written to the text file \$upgradeLogDir/ClassesForListInstances.txt. Results are written to bitmap files which can be loaded into the final converted GemStone/S 64 Bit v2.4.5 repository.

8. Log in to the v6.x system and reset the SystemUser password to 'swordfish':

```
topaz 1> printit
(AllUsers userWithId: #SystemUser) password: 'swordfish' .
System commitTransaction .
%
```

The conversion scripts log in with the SystemUser account and the default password.

9. Halt all user activity on the repository you are going to convert:

- a. Log in to Topaz as DataCurator.
- b. Force all other users off the system:

```
topaz 1> printit
System stopOtherSessions.
%
```

CAUTION

You MUST file out any changes that you have made to the GemStone/S kernel classes in order to preserve these changes in version 2.4.5. Also, consider saving important modified files, such as configuration files, that will be overwritten during the conversion.

10. File out any modifications or additions you made to GemStone/S kernel class methods by using the Topaz command **fileout**. For more information about fileout, see the *GemStone Topaz Programming Environment*.
11. Logout, and exit topaz.
12. Set the environment variable that will hold the upgrade log files.

C shell:

```
% setenv upgradeLogDir tempDir
```

Bourne or Korn shell:

```
$ upgradeLogDir=tempDir
$ export upgradeLogDir
```

Where *tempDir* is a temporary directory for which you have write permission.

NOTE

Use a separate log directory for each repository you convert.

13. Run the GemStone/S 64 Bit 2.4.5 script **convprep6x**. This script is in the upgrade directory of the 2.4.5 product tree; this should not be in your path, so it will need to be invoked with an explicit path. For example,

```
% $GEMSTONE_64/upgrade/convprep6x -s stoneName66
```

This script has the following options:

```
convprep6x [-h] [-s <stonename>]
```

-h prints this usage information.

-s <stoneName> sets the name of the running v6.x Stone to scan; if this option is not used, the script will default to **gemserver63**.

The **convprep6x** script scans the v6.x repository and produces files that are used in the second phase of conversion. These files are written to **\$upgradeLogDir**. The **convprep6x** script will write progress messages to stdout. When it completes, it will report:

```
convprep6x[INFO]: ...conversion preparation complete.
```

If this output is not produced, check the log files in the **\$upgradeLogDir** directory for information.

This script also shuts down the Stone.

While the v6.x system is not substantially affected by conversion preparation and remains completely usable, do not restart or use these extents until the conversion is complete.

Prepare for Conversion

1. Set up the configuration for GemStone/S 64 Bit 2.4.5. In particular, you should examine and update:
 - a. **DBF_EXTENT_SIZES**. The conversion process creates new v2.4.5 extents based on the v6.x extents; the v2.4.5 extents will be 20% to 200% larger. If this is the pilot, estimate the new size; if you are pre-growing extents allow for the larger growth.
For the production conversion, set the new sizes based on growth information from the pilot conversion.
 - b. **DBF_PRE_GROW**. We recommend setting this to true for the conversion process, in particular for the production conversion. This ensures that you will not run out of disk space during the conversion process.
 - c. **STN_TRAN_LOG_DIRECTORIES**. For large repositories, we recommend setting the tranlogs to `/dev/null` for the conversion process. Tranlogs from the conversion process are not useful.
 - d. **SHR_PAGE_CACHE_SIZE_KB**. To ensure the performance of the v2.4.5 system equals that of the v6.x system, the shared page cache size, for all shared caches including the gem server SPC, should be increased by the same percentage as the

growth in the extent files. If this is the pilot, start by estimating this to increase by 50%. It is important that the entire object table fit into the SPC.

For the production conversion, use the increase computed from growth information from the pilot conversion.

`GEM_TEMPOBJ_CACHE_SIZE`, `GEM_PRIVATE_PAGE_CACHE_KB`, and `STN_PRIVATE_PAGE_CACHE_KB` do not need to be increased.

2. Ensure that you have adequate disk space for the v2.4.5 extents in addition to the v6.x extents, as well as for tranlogs (if not using `/dev/null`) and a backup following the conversion.

For the pilot conversion, allow for a growth of as much as 200%. In other words, if your repository extents total size currently is 1GB, ensure you have at least 2GB free space for the 2.4.5 extents.

3. Set the `$GEMSTONE` and `$path` environment variables required for GemStone/S 64 Bit.

C shell:

```
% setenv GEMSTONE InstallDir245
% set path = ($GEMSTONE/bin $path)
```

Bourne or Korn shell:

```
$ GEMSTONE=InstallDir245
$ export GEMSTONE
$ export PATH=$GEMSTONE/bin:$PATH
```

where `InstallDir245` is the GemStone/S 64 Bit version 2.4.5 installation. You will no longer need the `$GEMSTONE_64` environment variable.

The `$upgradeLogDir` environment variable that was defined in the section 'Preprocessing in Old Environment' (see step 12 on page 30) must be available and set to the same directory.

4. Copy a clean v2.4.5 `extent0.dbf` to the location specified by the first entry in the of extent files, as it appears in the `DBF_EXTENT_NAMES` parameter setting in the configuration file that will be used by the 2.4.5 repository. For example,

```
% cp $GEMSTONE/bin/extent0.bdf $GEMSTONE/data
% chmod a+w $GEMSTONE/data/extent0.dbf
```

New extent files for v2.4.5 will be created as part of conversion. **Do not** copy your version 6.x extent files. All 6.x extents should be available in their 6.x locations.

Perform the Conversion and Upgrade

1. Start the 2.4.5 Stone

```
% startstone stoneName245
```

2. Extent conversion is performed by the script `conv6xTo2x`. This script is in the v2.4.5 product tree, and does not require an explicit path.

This script requires as an argument the configuration file used by the v6.x installation. This configuration file must not have the extent file names specified using `$GEMSTONE`.

It also has optional switches to specify the Stone name, the number of gems performing the conversion, and the number of OOPs per commit.

This script also includes the `-L` switch that enables recording of all references to Large Integers, and the `-F` switch to record all references to Float or SmallFloat. The conversion process does not convert instances of LargePositive- or LargeNegativeIntegers that fall within the new SmallIntegers range, nor instances of Float or SmallFloat that are representable as instances of SmallDouble. This can be done as an optional manual step following conversion. Note that using the `-L` or `-F` options will slow down the conversion process, since each object must be checked for references.

```
conv6xTo2x -e <oldSysConf> [-h] [-s <stoneName>] [-n <numConversionGems>] [-o <oopsPerCommit>] [-F] [-L]
-e <oldSysConf> specifies the configuration file to use. This configuration file must contain the list of 6.x extents to read data from. This is required; the script will not run without this information.
-h prints this usage information.
-s <stoneName> sets the name of the running stone to convert; if this option is not used, the script will default to gs64stone.
-n <numConversionGems> sets the number of parallel gems that will do the conversion; if this option is not used, the script will default to use one.
-o <oopsPerCommit> sets the number of oops per transaction; if this option is not used, the script will default to use 1000000.
-F During conversion, determine which objects reference one or more instances of Float for SmallFloat and write the object IDs to the binary bitmap file:
$upgradeLogDir/AllFloatRefs.bm.
-L During conversion, determine which objects reference one or more instances of LargePositiveInteger or LargeNegativeInteger and write the object IDs to the binary bitmap file: $upgradeLogDir/AllLrgIntRefs.bm
```

For example,

```
% conv6xTo2x -e installLocation66/data/system.conf -s stoneName245
```

The **conv6xTo2x** script will write progress messages to stdout. When it completes, it will report:

```
conv6xTo2x[INFO]: Successful conversion.
```

The stone will shut down at the completion of the `conv6xTo2x` step. This may take some time as the conversion gems terminate. Wait until the stone has completed and shut down before continuing.

3. Restart the 2.4.5 Stone

```
% startstone stoneName64
```

4. Run the script that performs the kernel class filein to upgrade the image.

The image upgrade is performed by the script `upgradeImageFrom6x`. This script has optional switches to specify the stone name and to set to size of the `GEM_TEMPOBJ_CACHE_SIZE` used for the upgrade process.

```
upgradeImageFrom6x [-h] [-c <cacheSize>] [-s <stoneName>]
-h prints this usage information.
-c <cacheSize> sets the size of the GEM_TEMPOBJ_CACHE_SIZE; if this is not
used, the script will default to use a value of 100000.
-s <stoneName> sets the name of the running stone to upgrade; if this option is
not used, the script will default to gs64stone.
```

For example,

```
% upgradeImageFrom6x -s stoneName245
```

The script will prompt you to press the return key to begin.

The script invokes subordinate scripts to complete the upgrade. The upgrade process will take some time.

The script should complete with the message:

```
Upgrade completed. No errors detected.
```

If not, please preserve the Stone log file and the contents of `$upgradeLogDir`. Contact your internal GemStone support person or GemStone Technical Support.

5. To convert large objects found during the conversion process, run the `postconv` script. This script has optional flags to specify stone name and the number of sessions to use.

```
postconv [-c <numCacheWarmerGems>] [-h] [-s <stoneName>]
[-n <numberOfSessions>] [-t <tempObjCacheSize>]
-c <numCacheWarmerGems> specifies the number of cache warmer gems to start
before starting post conversion; if this is not specified, no cache warmer gems are
started.
-h prints this usage information.
-s <stoneName> sets the name of the running stone to scan; if this option is not
used, the script will default to gs64stone.
-n <numberOfSessions> sets the number of parallel sessions to run to perform the
large object conversion. If this option is not specified, the script will default to one.
-t <tempObjCacheSize> sets the size of GEM_TEMPOBJ_CACHE_SIZE in KB; by
default, the same value as that used in the upgradeImage step, which defaults to
200000.
```

For example,

```
% postconv -s stoneName245
```

The `postconv` script will write progress messages to stdout. When it completes, it will report:

```
postconv[INFO]: Success! Conversion process from GemStone 6.3.x
or later to GemStone64 2.x completed.
```

6. If this is the pilot conversion, run an object audit and a page audit to verify the integrity of the repository following the conversion.

- If you set up `#ConversionClassesToFind` in your v6.x repository, be sure to remove this variable to avoid retaining references. Log in as `SystemUser`, execute:

```
UserGlobals removeKey: #ConversionClassesToFind.
```

and commit.

- Optional: If you set up `#ConversionClassesToFind` in your v6.x repository in order to collect instances of specified classes, the results will be written to bitmap files in the `$upgradeLogDir` directory.

There will be one file per Class, the file will have a name of the form:

```
<ClassName>_<oldOop>_<newOop>.bm
```

where:

`<className>` - Name of the class .

`<oldOop>` - GemStone/S v6.x OOP of the class.

`<newOop>` - GemStone/S 64 Bit v2.4.5 OOP of the class.

GemStone/S 64 Bit v2.4.5 contains Smalltalk methods to load bitmap files into customer-usable hidden sets. From these hidden sets, any required postconversion processing of the instances of these classes can be done.

- Optional: if you specified tracking of references to Large Integers or Floats, by using the `-L` or `-F` options during the `conv6xTo2x` script execution, the results will be written to a bitmap file:

```
$upgradeLogDir/AllLrgIntRefs.bm
```

```
$upgradeLogDir/AllFloatRefs.bm
```

GemStone/S 64 Bit v2.4.5 contains Smalltalk methods to load bitmap files into customer-usable hidden sets. From these hidden sets, you may load the individual objects and manually update the references.

Restore Your Site-Specific Settings and Back Up the Repository

- Reinstall any other GemStone products that modify kernel classes.

If you use GemConnect or GemBuilder for Java, you must install it again at this time. Use the procedure in the installation guide for that product.

- Log in to GemStone/S 64 Bit version 2.4.5 as `DataCurator`.
- Change the password for `SystemUser`, which you changed to `swordfish` prior to the conversion, back to its previous value. Also, change the passwords for `GcUser` and `DataCurator`, which were reset by the conversion process, back to the version previous value:

```
topaz 1> printit
```

```
(AllUsers userWithId: 'SystemUser') password: '66Password'.
```

```
(AllUsers userWithId: 'GcUser') password: '66Password'.
```

```
(AllUsers userWithId: 'DataCurator') password: '66Password'.
```

```
System commitTransaction
```

```
%
```

where *66Password* is the account password used in the original GemStone/S v6.x repository.

The converted repository is now usable. Other users can log in to assist with the following steps.

4. If you have modified any kernel class methods of the previous version, carefully compare your changes with version 2.4.5 kernel methods to see whether your changes are still necessary or appropriate. If so, file in the changes and commit.
5. Create a full backup of the converted repository. For details, see the *System Administration Guide for GemStone/S 64 Bit*.
6. If you are using GBS clients, configure these to use the version 2.4.5 client libraries. See Chapter 4, 'Configuring GBS for GemStone/S 64 Bit' for details.

Detecting Oversize Methods

Methods larger than 65K are not supported in GemStone/S 64 Bit, and cannot be loaded or executed. If your GemStone/S version 6.x repository contains methods larger than this limit, these methods must be factored into multiple smaller methods before the repository is converted; this task cannot be done after conversion.

GemStone/S 64 Bit 2.4.5 provides a script to detect if any methods exceed the size limit. To use this script, the GemStone/S version 6.x repository that you wish to verify must be running, and not yet converted to GemStone/S 64 Bit, and GemStone/S 64 Bit 2.4.5 must have been installed.

1. Ensure that a stone is running on the GemStone/S version 6.x repository.
2. Verify that GemStone/S 64 Bit 2.4.5 is installed
3. Start topaz, and log in to the GemStone/S version 6.x repository as SystemUser.
4. Execute the script `methodsTooLargeFor64.topaz`. For example,

```
topaz 1>input gs64install/upgrade/methodsTooLargeFor64.topaz
```

where *gs64install* is the installation directory for GemStone/S 64 Bit 2.4.5.
5. Wait for the scan to complete. This will take some time as it scans all extents for instances of GsMethod. When it completes, log out and exit topaz.
6. The script prints the results of the scan both to standard out and to a text file `methodsToLargeFor64Report.log`, in the working directory. This report provides details on any methods that are exceed the size limit, including the current size, class and selector. If there are methods that exceed the size limit, factor these into multiple smaller methods and commit.
7. Execute a `markForCollection` and allow reclaim to complete, before rerunning the script to verify that the modified methods are now of appropriate size. Otherwise, the script may detect old instances of methods that have not yet been garbage collected.

Configuring GBS for GemStone/S 64 Bit

This chapter describes how to configure your GemBuilder for Smalltalk (GBS) application to run with GemStone/S 64 Bit version 2.4.5.

NOTE

GemStone/S 64 Bit version 2.4.5 requires the use of GBS version 7.1.2patch2 or later; version 7.4 or later is recommended. VA Smalltalk applications must use GBS version 5.3.x; version 5.3.2 is recommended. For upgrade instructions, refer to the GemBuilder for Smalltalk Installation Guide.

For the supported versions of client Smalltalk, see “Supported platforms” on page 38.

In addition to using the appropriate version of GBS, you must use GemStone/S 64 Bit 2.4.5 client libraries to be able to log in to the GemStone/S 64 Bit 2.4.5 server.

On Unix platforms, GemStone/S 64 Bit 2.4.5 provides both 64-bit libraries and 32-bit libraries. To load client libraries into the VisualWorks or VA Smalltalk 32-bit process, the 32-bit libraries must be used. 64-bit and 32 bit libraries have identical names, and are provided in separate directories to distinguish them.

VisualWorks 32-bit client applications and VA Smalltalk client applications can only log in RPC to GemStone/S 64 Bit.

VisualWorks 64-bit applications can load the 64-bit client libraries, and can login linked as well as RPC.

The following sections describes the procedure for installing client libraries and getting GBS to recognize them.

Supported platforms

The following tables list supported versions of GemBuilder for Smalltalk with the compatible versions of client Smalltalk and Operating System.

GBS version 7.4

GemBuilder for Smalltalk version 7.4 is supported with GemStone/S 64 Bit version 2.4.5, on the following VisualWorks and OS platforms:

VW 7.8 32-bit	VW 7.8 64-bit	VW 7.7.1 32-bit	VW 7.7.1 64-bit
<ul style="list-style-type: none"> ▶ Windows XP, Windows 2003, Windows Vista, and Windows 7 ▶ Solaris 9 and 10 on SPARC ▶ SuSE Linux ES 10 and 11, Red Hat Linux ES 5.0, 5.5, and 6.1 	<ul style="list-style-type: none"> ▶ Solaris 10 on SPARC ▶ SuSE Linux ES 10 and 11, Red Hat Linux ES 5.0, 5.5, and 6.1 	<ul style="list-style-type: none"> ▶ Windows XP, Windows 2003, Windows Vista, and Windows 7 ▶ Solaris 9 and 10 on SPARC ▶ SuSE Linux ES 10, Red Hat Linux ES 5.0 and 5.5 	<ul style="list-style-type: none"> ▶ Solaris 10 on SPARC ▶ SuSE Linux ES 10, Red Hat Linux ES 5.0 and 5.5

GBS version 7.3.3

GemBuilder for Smalltalk version 7.3.3 is supported with GemStone/S 64 Bit version 2.4.5, on the following VisualWorks and OS platforms:

VW 7.7.1 32-bit	VW 7.7.1 64-bit	VW 7.7 32-bit	VW 7.7 64-bit
<ul style="list-style-type: none"> ▶ Windows XP, Windows 2003, Windows Vista, and Windows 7 ▶ Solaris 9 and 10 on SPARC ▶ SuSE Linux ES 10, Red Hat Linux ES 5.0 and 5.5 	<ul style="list-style-type: none"> ▶ Solaris 10 on SPARC ▶ SuSE Linux ES 10, Red Hat Linux ES 5.0 and 5.5 	<ul style="list-style-type: none"> ▶ Windows XP, Windows 2003, Windows Vista, and Windows 7 ▶ Solaris 9 and 10 on SPARC ▶ SuSE Linux ES 10, Red Hat Linux ES 5.0 and 5.5 	<ul style="list-style-type: none"> ▶ Solaris 10 on SPARC ▶ SuSE Linux ES 10, Red Hat Linux ES 5.0 and 5.5

GBS version 5.3.2

GemBuilder for Smalltalk version 5.3.2 is supported with GemStone/S 64 Bit version 2.4.5, on the following VA Smalltalk and OS platforms:

VA Smalltalk 8.0.2	VA Smalltalk 7.5.2
<ul style="list-style-type: none"> ▶ Windows 2008 (64-bit), Windows 7 (32- and 64-bit), Windows XP (32-bit) 	<ul style="list-style-type: none"> ▶ Windows 2003 Server, Windows XP

For more details on supported platforms and requirements, see the Release Notes for that version of GemBuilder for Smalltalk.

GemStone/S 64 Bit 2.4.5 Windows Client Installation

To allow GemStone/S 64 Bit clients to connect and perform some operations on Windows, GemStone/S 64 Bit provides a separate Windows installation, with the name GemBuilder for C. This installation provides:

- ▶ The ability to run topaz on Windows, to login RPC to a GemStone/S 64 Bit server on UNIX.
- ▶ The ability to run gslis -m on Windows, to check the status of GemStone/S 64 Bit 2.x servers on UNIX.
- ▶ The client libraries to be used by GBS for RPC logins.

If you do not require topaz or gslis on Windows, you may wish to extract only the client libraries from the Windows installation, and move these files to a directory on the path or to the GBS installation. See “Installing the GemStone/S 64 Bit 2.4.5 Libraries onto Windows Clients” on page 4-39

To install the GemStone/S 64 Bit Windows Client product, use the following procedure. The procedure is similar regardless of what platform the GemStone/S 64 Bit server is running on.

1. The GemStone/S 64 Bit client installation for Windows is provided as a zipped archive with a name similar to GemBuilderC2.4.5-x86.Windows_NT.zip. Move this distribution file to the directory location in which this will be installed.
2. Create a directory named GemBuilderC2.4.5-x86.Windows_NT, into which the client will be installed, and make this directory the working directory. For example:

```
C:\InstallDir> mkdir GemBuilderC2.4.5-x86.Windows_NT  
C:\InstallDir> cd GemBuilderC2.4.5-x86.Windows_NT
```

3. Unzip the distribution file using unzip. For example,

```
C:\InstallDir\GemBuilderC2.4.5-x86.Windows_NT> unzip  
GemBuilderC2.4.5-x86.Windows_NT.zip
```

In addition to several subdirectories, C:\InstallDir\GemBuilderC2.4.5-x86.Windows_NT also contains two text files: PACKING.txt, which lists all of the GemStone files, and version.txt, which identifies the product and release.

4. Add the directory

```
C:\InstallDir\GemBuilderC2.4.5-x86.Windows_NT\bin  
to the machine search path.
```

Installing the GemStone/S 64 Bit 2.4.5 Libraries onto Windows Clients

This section describes the procedure for installing client libraries on Windows and getting GBS to recognize them.

1. Quit any running client Smalltalk VM that is using GBS.
2. Your client libraries may be placed in the directory in which the client Smalltalk executable resides, or in any directory that is on the path, %PATH%.

NOTE

In step 3., <GBS> refers to the directory in which the client Smalltalk executable resides, or any directory that is on the path that will be used by the GBS application, and <SRC> refers to the GemStone/S 64 Bit Windows client installation directory (for example, `installDir/GemBuilderC2.4.5-x86.Windows_NT/bin`).

- To copy the files from the GemStone/S 64 Bit Windows client directory <SRC> to the GemBuilder installation directory, or another directory on the Windows path, <GBS>, execute the following:

```
C:\> copy <SRC>\libgcirpc64-2.4.5.dll <GBS>
C:\> copy <SRC>\libgcirpc.dll <GBS>
C:\> copy <SRC>\libgs64-2.4.5.dll <GBS>
```

NOTE

The shared library name includes exactly three digits of the server version number. If the server version number contains a larger or smaller number of digits, it is truncated or extended with zeros to make these three digits.

- Ensure that there are no other copies of these libraries on the search path.
- If the GBS configuration parameter `libraryName` is not set, or is set to `libgcirpc.dll`, installation is complete. The correct client library will be loaded when the client Smalltalk VM is restarted and the application logs in to GemStone. If the `libraryName` is set to something else, for example if you are upgrading from 32-bit GemStone/S, you will need to update this to the correct library name. If this is necessary, continue with the following steps. Start up the client Smalltalk VM.
- Clear the library name. There are several ways to do this. Using the GBS settings dialog, select the tab titled "Server Communication", and clear the field `libraryName`. You may also execute:

```
GbsConfiguration current libraryName: ''
```

- Save your image, exit, and restart, to allow the correct libraries to be loaded.

Installing the GemStone/S 64 Bit 2.4.5 Libraries onto Unix Clients

GemStone/S 64 Bit supports GBS clients running on Solaris and Linux with 32-bit or 64-bit VisualWorks. Since 32-bit process can only load 32-bit libraries, and 64-bit processes can only load 64-bit libraries, GemStone provides both 64-bit and 32-bit libraries. These libraries have identical names, and are provided in separate directories to distinguish them.

For 32-bit VisualWorks applications, you will use the libraries in the `lib32` subdirectory of the GemStone/S 64 Bit installation; `$GEMSTONE/lib32/`.

For 64-bit VisualWorks applications, you will use the libraries in the `lib` subdirectory of the GemStone/S 64 Bit installation; `$GEMSTONE/lib/`.

- Log in to your GBS client machine as the user who is the owner of the GBS installation files.

- Your client libraries may be placed in any directory that is on the machine search path `$LD_LIBRARY_PATH`, or you may add the directory containing the client libraries to the `$LD_LIBRARY_PATH`. Ensure that there are no other copies of the client libraries on the search path. (In the following instructions, the term “path” means the path specified by `$LD_LIBRARY_PATH`)

Alternatively, you can place the shared libraries in any location, and in the GBS configuration parameter *libraryName*, specify the absolute path to the client library file.

NOTE

In step 3, <GBS> refers to your GemBuilder installation directory, or any directory that is on the path that will be used by the GBS application, and <SRC> refers to the lib32 or lib subdirectory of your installation (for example, `installDir/GemStone64Bit2.4.5-sparc.Solaris/lib32`) or `installDir/GemStone64Bit2.4.5-sparc.Solaris/lib`).

- To copy the files from the GemStone/S 64 Bit server source directory `<SRC>` to the GemBuilder installation directory, or another directory, `<GBS>`, execute the following:

```
% cp <SRC>/libgcirpc64-2.4.5.so <GBS>
```

NOTE

The shared library name includes exactly three digits of the server version number. If the server version number contains a larger or smaller number of digits, it is truncated or extended with zeros to make these three digits.

- Make the destination directory the current working directory, and create a symbolic link to the library:

```
% cd <GBS>
% ln -s libgcirpc64-2.4.5.so libgcirpc.so
```

- If the client libraries are in a directory on the path, and the GBS configuration parameter *libraryName* is not set, or is set to `libgcirpc.so`, installation is complete. The correct client library will be loaded after the client Smalltalk VM is restarted, on login.

If the *libraryName* is set to something else, for example if you are upgrading from 32-bit GemStone/S, you will need to update this to the correct library name. If this is necessary, continue with the following steps.

- Start up the client Smalltalk VM.
- Set the library name. There are several ways to do this. Using the GBS settings dialog, select the tab titled “Server Communication”, and fill in the appropriate library name in the *libraryName* field. You may also execute:

```
GbsConfiguration current libraryName: '<libraryName>'
```

If the clientLibraries are in a directory on the path, clear the *libraryName* field, or set it to an empty string. The default client library search will find and load the correct library.

If the client libraries are not in a directory on the path, *libraryName* must be set to the absolute path and name of the client library `libgcirpc.so`.

- Save your image, exit, and restart, to allow the correct libraries to be loaded.